

NAG Library Routine Document

D03PYF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

D03PYF may be used in conjunction with either D03PDF/D03PDA or D03PJF/D03PJA. It computes the solution and its first derivative at user-specified points in the spatial coordinate.

2 Specification

```

SUBROUTINE D03PYF (NPDE, U, NBKPTS, XBKPTS, NPOLY, NPTS, XP, INTPTS,      &
                  ITYPE, UP, RSAVE, LRSAVE, IFAIL)
INTEGER            NPDE, NBKPTS, NPOLY, NPTS, INTPTS, ITYPE, LRSAVE,      &
                  IFAIL
REAL (KIND=nag_wp) U(NPDE,NPTS), XBKPTS(NBKPTS), XP(INTPTS),          &
                  UP(NPDE,INTPTS,ITYPE), RSAVE(LRSAVE)

```

3 Description

D03PYF is an interpolation routine for evaluating the solution of a system of partial differential equations (PDEs), or the PDE components of a system of PDEs with coupled ordinary differential equations (ODEs), at a set of user-specified points. The solution of a system of equations can be computed using D03PDF/D03PDA or D03PJF/D03PJA on a set of mesh points; D03PYF can then be employed to compute the solution at a set of points other than those originally used in D03PDF/D03PDA or D03PJF/D03PJA. It can also evaluate the first derivative of the solution. Polynomial interpolation is used between each of the break-points $XBKPTS(i)$, for $i = 1, 2, \dots, NBKPTS$. When the derivative is needed ($ITYPE = 2$), the array $XP(INTPTS)$ must not contain any of the break-points, as the method, and consequently the interpolation scheme, assumes that only the solution is continuous at these points.

4 References

None.

5 Parameters

Note: the parameters U, NPTS, NPDE, XBKPTS, NBKPTS, RSAVE and LRSAVE must be supplied unchanged from either D03PDF/D03PDA or D03PJF/D03PJA.

- 1: NPDE – INTEGER *Input*
On entry: the number of PDEs.
Constraint: $NPDE \geq 1$.
- 2: U(NPDE, NPTS) – REAL (KIND=nag_wp) array *Input*
On entry: the PDE part of the original solution returned in the parameter U by the routine D03PDF/D03PDA or D03PJF/D03PJA.
- 3: NBKPTS – INTEGER *Input*
On entry: the number of break-points.
Constraint: $NBKPTS \geq 2$.

- 4: XBKPTS(NBKPTS) – REAL (KIND=nag_wp) array Input
On entry: XBKPTS(i), for $i = 1, 2, \dots, \text{NBKPTS}$, must contain the break-points as used by D03PDF/D03PDA or D03PJF/D03PJA.
Constraint: XBKPTS(1) < XBKPTS(2) < \dots < XBKPTS(NBKPTS).
- 5: NPOLY – INTEGER Input
On entry: the degree of the Chebyshev polynomial used for approximation as used by D03PDF/D03PDA or D03PJF/D03PJA.
Constraint: $1 \leq \text{NPOLY} \leq 49$.
- 6: NPTS – INTEGER Input
On entry: the number of mesh points as used by D03PDF/D03PDA or D03PJF/D03PJA.
Constraint: NPTS = (NBKPTS – 1) \times NPOLY + 1.
- 7: XP(INTPTS) – REAL (KIND=nag_wp) array Input
On entry: XP(i), for $i = 1, 2, \dots, \text{INTPTS}$, must contain the spatial interpolation points.
Constraints:

$$\text{XBKPTS}(1) \leq \text{XP}(1) < \text{XP}(2) < \dots < \text{XP}(\text{INTPTS}) \leq \text{XBKPTS}(\text{NBKPTS});$$
 if ITYPE = 2, $\text{XP}(i) \neq \text{XBKPTS}(j)$, for $i = 1, 2, \dots, \text{INTPTS}$ and $j = 2, 3, \dots, \text{NBKPTS} - 1$.
- 8: INTPTS – INTEGER Input
On entry: the number of interpolation points.
Constraint: INTPTS ≥ 1 .
- 9: ITYPE – INTEGER Input
On entry: specifies the interpolation to be performed.
 ITYPE = 1
 The solution at the interpolation points are computed.
 ITYPE = 2
 Both the solution and the first derivative at the interpolation points are computed.
Constraint: ITYPE = 1 or 2.
- 10: UP(NPDE, INTPTS, ITYPE) – REAL (KIND=nag_wp) array Output
On exit: if ITYPE = 1, UP($i, j, 1$), contains the value of the solution $U_i(x_j, t_{\text{out}})$, at the interpolation points $x_j = \text{XP}(j)$, for $j = 1, 2, \dots, \text{INTPTS}$ and $i = 1, 2, \dots, \text{NPDE}$.
 If ITYPE = 2, UP($i, j, 1$) contains $U_i(x_j, t_{\text{out}})$ and UP($i, j, 2$) contains $\frac{\partial U_i}{\partial x}$ at these points.
- 11: RSAVE(LRSAVE) – REAL (KIND=nag_wp) array Communication Array
 The array RSAVE contains information required by D03PYF as returned by D03PDF/D03PDA or D03PJF/D03PJA. The contents of RSAVE must not be changed from the call to D03PDF/D03PDA or D03PJF/D03PJA. Some elements of this array are overwritten on exit.
- 12: LRSAVE – INTEGER Input
On entry: the size of the workspace RSAVE, as in D03PDF/D03PDA or D03PJF/D03PJA.

13: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1 , explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, ITYPE \neq 1 or 2,
 or NPOLY $<$ 1,
 or NPDE $<$ 1,
 or NBKPTS $<$ 2,
 or INTPTS $<$ 1,
 or NPTS \neq (NBKPTS $-$ 1) \times NPOLY + 1,
 or XBKPTS(i), for $i = 1, 2, \dots, \text{NBKPTS}$, are not ordered.

IFAIL = 2

On entry, the interpolation points XP(i), for $i = 1, 2, \dots, \text{INTPTS}$, are not in strictly increasing order, or when ITYPE = 2, at least one of the interpolation points stored in XP is equal to one of the break-points stored in XBKPTS.

IFAIL = 3

You are attempting extrapolation, that is, one of the interpolation points XP(i), for some i , lies outside the interval [XBKPTS(1), XBKPTS(NBKPTS)]. Extrapolation is not permitted.

IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.
 See Section 3.8 in the Essential Introduction for further information.

IFAIL = -399

Your licence key may have expired or may not have been installed correctly.
 See Section 3.7 in the Essential Introduction for further information.

IFAIL = -999

Dynamic memory allocation failed.
 See Section 3.6 in the Essential Introduction for further information.

7 Accuracy

See the documents for D03PDF/D03PDA or D03PJF/D03PJA.

8 Parallelism and Performance

Not applicable.

9 Further Comments

None.

10 Example

See Section 10 in D03PDF/D03PDA.
