NAG Library Routine Document

F11MEF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F11MEF computes the LU factorization of a real sparse matrix in compressed column (Harwell–Boeing), column-permuted format.

2 Specification

SUBROUTINE F11MEF (N, IROWIX, A, IPRM, THRESH, NZLMX, NZLUMX, NZUMX, IL,
LVAL, IU, UVAL, NNZL, NNZU, FLOP, IFAIL)&INTEGERN, IROWIX(*), IPRM(7*N), NZLMX, NZLUMX, NZUMX,
IL(7*N+NZLMX+4), IU(2*N+NZUMX+1), NNZL, NNZU, IFAIL
REAL (KIND=nag_wp) A(*), THRESH, LVAL(NZLUMX), UVAL(NZUMX), FLOP

3 Description

Given a real sparse matrix A, F11MEF computes an LU factorization of A with partial pivoting, $P_rAP_c = LU$, where P_r is a row permutation matrix (computed by F11MEF), P_c is a (supplied) column permutation matrix, L is unit lower triangular and U is upper triangular. The column permutation matrix, P_c , must be computed by a prior call to F11MDF. The matrix A must be presented in the column permuted, compressed column (Harwell–Boeing) format.

The LU factorization is output in the form of four one-dimensional arrays: integer arrays IL and IU and real-valued arrays LVAL and UVAL. These describe the sparsity pattern and numerical values in the L and U matrices. The minimum required dimensions of these arrays cannot be given as a simple function of the size parameters (order and number of nonzero values) of the matrix A. This is due to unpredictable fill-in created by partial pivoting. F11MEF will, on return, indicate which dimensions of these arrays were not adequate for the computation or (in the case of one of them) give a firm bound. You should then allocate more storage and try again.

4 References

Demmel J W, Eisenstat S C, Gilbert J R, Li X S and Li J W H (1999) A supernodal approach to sparse partial pivoting *SIAM J. Matrix Anal. Appl.* **20** 720–755

Demmel J W, Gilbert J R and Li X S (1999) An asynchronous parallel supernodal algorithm for sparse gaussian elimination *SIAM J. Matrix Anal. Appl.* **20** 915–952

5 Parameters

1: N – INTEGER

On entry: n, the order of the matrix A.

Constraint: $N \ge 0$.

2: IROWIX(*) - INTEGER array

Note: the dimension of the array IROWIX must be at least nnz, the number of nonzeros of the sparse matrix A.

On entry: the row index array of sparse matrix A.

Input

Input

Input

Input

Input/Output

3: A(*) - REAL (KIND=nag wp) array

Note: the dimension of the array A must be at least nnz, the number of nonzeros of the sparse matrix A.

On entry: the array of nonzero values in the sparse matrix A.

4: $IPRM(7 \times N) - INTEGER$ array

On entry: contains the column permutation which defines the permutation P_c and associated data structures as computed by routine F11MDF.

On exit: part of the array is modified to record the row permutation P_r determined by pivoting.

5: THRESH - REAL (KIND=nag_wp)

On entry: the diagonal pivoting threshold, t. At step j of the Gaussian elimination, if $|A_{jj}| \ge t \left(\max_{i \ge j} |A_{ij}| \right)$, use A_{jj} as a pivot, otherwise use $\max_{i \ge j} |A_{ij}|$. A value of t = 1 corresponds to partial pivoting, a value of t = 0 corresponds to always choosing the pivot on the diagonal (unless it is zero).

Suggested value: THRESH = 1.0. Smaller values may result in a faster factorization, but the benefits are likely to be small in most cases. It might be possible to use THRESH = 0.0 if you are confident about the stability of the factorization, for example, if A is diagonally dominant.

Constraint: $0.0 \leq \text{THRESH} \leq 1.0$.

6: NZLMX – INTEGER

On entry: indicates the available size of array IL. The dimension of IL should be at least $7 \times N + NZLMX + 4$. A good range for NZLMX that works for many problems is nnz to $8 \times nnz$, where nnz is the number of nonzeros in the sparse matrix A. If, on exit, IFAIL = 2, the given NZLMX was too small and you should attempt to provide more storage and call the routine again.

Constraint: NZLMX \geq 1.

7: NZLUMX – INTEGER

On entry: indicates the available size of array LVAL. The dimension of LVAL should be at least NZLUMX.

Constraint: NZLUMX \geq 1.

On exit: if IFAIL = 4, the given NZLUMX was too small and is reset to a value that will be sufficient. You should then provide the indicated storage and call the routine again.

8: NZUMX – INTEGER

On entry: indicates the available sizes of arrays IU and UVAL. The dimension of IU should be at least $2 \times N + NZUMX + 1$ and the dimension of UVAL should be at least NZUMX. A good range for NZUMX that works for many problems is nnz to $8 \times nnz$, where nnz is the number of nonzeros in the sparse matrix A. If, on exit, IFAIL = 3, the given NZUMX was too small and you should attempt to provide more storage and call the routine again.

Constraint: NZUMX ≥ 1 .

9:
$$IL(7 \times N + NZLMX + 4) - INTEGER$$
 array Output

On exit: encapsulates the sparsity pattern of matrix L.

 10:
 LVAL(NZLUMX) - REAL (KIND=nag_wp) array
 Output

On exit: records the nonzero values of matrix L and some of the nonzero values of matrix U.

Input/Output

Input/Output

11:	$IU(2 \times N + NZUMX + 1) - INTEGER$ array On exit: encapsulates the sparsity pattern of matrix U.	Output
12:	UVAL(NZUMX) – REAL (KIND=nag_wp) array On exit: records some of the nonzero values of matrix U.	Output
13:	NNZL – INTEGER On exit: the number of nonzero values in the matrix L .	Output
14:	NNZU – INTEGER On exit: the number of nonzero values in the matrix U.	Output
15:	FLOP – REAL (KIND=nag_wp) On exit: the number of floating-point operations performed.	Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry,	N < 0,
or	NZLMX < 1,
or	NZLUMX < 1 ,
or	NZUMX < 1,
or	THRESH < 0.0 ,
or	THRESH > 1.0 .

IFAIL = 2

NZLMX was not large enough. You should repeat the call with a larger value of NZLMX, providing more storage for the output array IL.

IFAIL = 3

NZUMX was not large enough. You should repeat the call with a larger value of NZUMX, providing more storage for the output arrays IU and UVAL.

IFAIL = 4

NZLUMX was not large enough. You should repeat the call with the value of NZLUMX returned on exit, providing more storage for the output array LVAL.

IFAIL = 5

The matrix A is singular and no factorization will be attempted.

IFAIL = 301

Unable to allocate required internal workspace.

IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.

See Section 3.8 in the Essential Introduction for further information.

IFAIL = -399

Your licence key may have expired or may not have been installed correctly.

See Section 3.7 in the Essential Introduction for further information.

IFAIL = -999

Dynamic memory allocation failed.

See Section 3.6 in the Essential Introduction for further information.

7 Accuracy

The computed factors L and U are the exact factors of a perturbed matrix A + E, where

 $|E| \le c(n)\epsilon |L||U|,$

c(n) is a modest linear function of n, and ϵ is the *machine precision*, when partial pivoting is used. If no partial pivoting is used, the factorization accuracy can be considerably worse. A call to F11MMF after F11MEF can help determine the quality of the factorization.

8 Parallelism and Performance

F11MEF is threaded by NAG for parallel execution in multithreaded implementations of the NAG Library.

F11MEF makes calls to BLAS and/or LAPACK routines, which may be threaded within the vendor library used by this implementation. Consult the documentation for the vendor library for further information.

Please consult the X06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this routine. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

9 Further Comments

The total number of floating-point operations depends on the sparsity pattern of the matrix A.

A call to F11MEF may be followed by calls to the routines:

F11MFF to solve AX = B or $A^{T}X = B$;

F11MGF to estimate the condition number of A;

F11MMF to estimate the reciprocal pivot growth of the LU factorization.

10 Example

This example computes the LU factorization of the matrix A, where

	(2.	00	1.00	0	0	0 \	١
	1	0	0	1.00	-1.00	0	
A =	4.	00	0	1.00	0	1.00	١.
		0	0	0	1.00	$\begin{array}{c} 1.00\\ 2.00\end{array}$	
		0	-2.00	0	0	3.00/	/

10.1 Program Text

Program fllmefe

```
!
      F11MEF Example Program Text
!
      Mark 25 Release. NAG Copyright 2014.
1
      .. Use Statements ..
      Use nag_library, Only: fllmdf, fllmef, nag_wp, x04cbf
1
      .. Implicit None Statement ..
      Implicit None
      .. Parameters ..
1
      Real (Kind=nag_wp), Parameter :: one = 1.E0_nag_wp
Integer, Parameter :: nin = 5, nout = 6
!
      .. Local Scalars ..
      Real (Kind=nag_wp)
                                           :: flop, thresh
                                           :: i, ifail, n, nnz, nnzl, nnzu, nzlmx, &
      Integer
                                               nzlumx, nzumx
      Character (1)
                                           :: spec
1
      .. Local Arrays ..
      Real (Kind=nag_wp), Allocatable :: a(:), lval(:), uval(:)
Integer, Allocatable :: icolzp(:), il(:), iprm(:),
irowix(:), iu(:)
                                                                                        &
                                           :: clabs(1), rlabs(1)
      Character (1)
      .. Executable Statements ..
1
      Write (nout,*) 'F11MEF Example Program Results'
      Flush (nout)
      Skip heading in data file
!
      Read (nin,*)
1
      Read order of matrix
      Read (nin,*) n
      Allocate (icolzp(n+1), iprm(7*n))
      Read the matrix A
!
      Read (nin,*) icolzp(1:n+1)
      nnz = icolzp(n+1) - 1
      Allocate (a(nnz),lval(8*nnz),uval(8*nnz),il(7*n+8*nnz+4),irowix(nnz), &
        iu(2*n+8*nnz+1))
      Do i = 1, nnz
        Read (nin,*) a(i), irowix(i)
      End Do
1
      Calculate COLAMD permutation
      spec = 'M'
1
      ifail: behaviour on error exit
               =0 for hard exit, =1 for quiet-soft, =-1 for noisy-soft
1
      ifail = 0
      Call f11mdf(spec,n,icolzp,irowix,iprm,ifail)
      Factorise
!
```

```
thresh = one
      ifail = 0
      nzlmx = 8*nnz
      nzlumx = 8*nnz
      nzumx = 8*nnz
      Call fllmef(n,irowix,a,iprm,thresh,nzlmx,nzlumx,nzumx,il,lval,iu,uval, &
        nnzl,nnzu,flop,ifail)
!
     Output results
      Write (nout,99999)
      Write (nout,99998) nnzl + nnzu - n
      Flush (nout)
      Call x04cbf('G','X',1,10,lval,1,'F7.2','Factor elements in LVAL','N', \&
      rlabs,'N',clabs,80,0,ifail)
Call x04cbf('G','X',1,4,uval,1,'F7.2','Factor elements in UVAL','N', &
        rlabs,'N',clabs,80,0,ifail)
99999 Format (1X/1X,'Number of nonzeros in factors (excluding unit', &
        / diagonal)/)
99998 Format (1X, I8)
    End Program fllmefe
```

10.2 Program Data

F11MEF Example Program Data 5 Ν 1 3 5 7 9 ICOLZP(I) I=1,..,N+1 12 2. 1 4. 3 1. 1 -2. 5 1. 2 3 1. -1. 2 1. 4 1. 3 2. 4 3. 5 A(I), IROWIX(I) I=1,...,NNZ

10.3 Program Results