# **NAG Library Routine Document**

### G05TFF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

# 1 Purpose

G05TFF generates a vector of pseudorandom integers from the discrete logarithmic distribution with parameter a.

# 2 Specification

```
SUBROUTINE GO5TFF (MODE, N, A, R, LR, STATE, X, IFAIL)

INTEGER MODE, N, LR, STATE(*), X(N), IFAIL

REAL (KIND=nag_wp) A, R(LR)
```

# 3 Description

G05TFF generates n integers  $x_i$  from a discrete logarithmic distribution, where the probability of  $x_i = I$  is

$$P(x_i = I) = -\frac{a^I}{I \times \log(1 - a)}, \quad I = 1, 2, \dots,$$

where 0 < a < 1.

The variates can be generated with or without using a search table and index. If a search table is used then it is stored with the index in a reference vector and subsequent calls to G05TFF with the same parameter value can then use this reference vector to generate further variates.

One of the initialization routines G05KFF (for a repeatable sequence if computed sequentially) or G05KGF (for a non-repeatable sequence) must be called prior to the first call to G05TFF.

### 4 References

Knuth D E (1981) The Art of Computer Programming (Volume 2) (2nd Edition) Addison-Wesley

# 5 Parameters

1: MODE – INTEGER Input

On entry: a code for selecting the operation to be performed by the routine.

MODE = 0

Set up reference vector only.

MODE = 1

Generate variates using reference vector set up in a prior call to G05TFF.

MODE = 2

Set up reference vector and generate variates.

MODE = 3

Generate variates without using the reference vector.

Constraint: MODE = 0, 1, 2 or 3.

Mark 25 G05TFF.1

G05TFF NAG Library Manual

2: N – INTEGER Input

On entry: n, the number of pseudorandom numbers to be generated.

Constraint:  $N \ge 0$ .

3:  $A - REAL (KIND=nag_wp)$ 

Input

On entry: a, the parameter of the logarithmic distribution.

Constraint: 0.0 < A < 1.0.

4: R(LR) - REAL (KIND=nag\_wp) array

Communication Array

On entry: if MODE = 1, the reference vector from the previous call to G05TFF.

If MODE = 3, R is not referenced.

On exit: MODE  $\neq$  3, the reference vector.

5: LR – INTEGER Input

On entry: the dimension of the array R as declared in the (sub)program from which G05TFF is called.

Suggested value:

if MODE 
$$\neq$$
 3, LR = 18 +  $\frac{40}{1-A}$ ; otherwise LR = 1.

Constraints:

if MODE = 0 or 2, LR must not be too small, but the lower limit is too complicated to specify;

if MODE = 1, LR must remain unchanged from the previous call to G05TFF.

6: STATE(\*) – INTEGER array

Communication Array

**Note**: the actual argument supplied **must** be the array STATE supplied to the initialization routines G05KFF or G05KGF.

On entry: contains information on the selected base generator and its current state.

On exit: contains updated information on the state of the generator.

7: X(N) - INTEGER array

Output

On exit: the n pseudorandom numbers from the specified logarithmic distribution.

8: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

G05TFF.2 Mark 25

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

### IFAIL = 1

On entry, MODE =  $\langle value \rangle$ . Constraint: MODE = 0, 1, 2 or 3.

#### IFAIL = 2

On entry,  $N = \langle value \rangle$ . Constraint:  $N \ge 0$ .

### IFAIL = 3

On entry,  $A = \langle value \rangle$ . Constraint: 0.0 < A < 1.0.

#### IFAIL = 4

On entry, some of the elements of the array R have been corrupted or have not been initialized.

The value of A is not the same as when R was set up in a previous call.

Previous value of  $A = \langle value \rangle$  and  $A = \langle value \rangle$ .

#### IFAIL = 5

On entry, LR is too small when MODE = 0 or 2: LR =  $\langle value \rangle$ , minimum length required =  $\langle value \rangle$ .

#### IFAIL = 6

On entry, STATE vector has been corrupted or not initialized.

# IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.

See Section 3.8 in the Essential Introduction for further information.

#### IFAIL = -399

Your licence key may have expired or may not have been installed correctly.

See Section 3.7 in the Essential Introduction for further information.

#### IFAIL = -999

Dynamic memory allocation failed.

See Section 3.6 in the Essential Introduction for further information.

# 7 Accuracy

Not applicable.

### 8 Parallelism and Performance

G05TFF is threaded by NAG for parallel execution in multithreaded implementations of the NAG Library.

Mark 25 G05TFF.3

G05TFF NAG Library Manual

Please consult the X06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this routine. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

### **9** Further Comments

None.

# 10 Example

This example prints 10 pseudorandom integers from a logarithmic distribution with parameter a = 0.9999, generated by a single call to G05TFF, after initialization by G05KFF.

### 10.1 Program Text

```
Program g05tffe
     GO5TFF Example Program Text
     Mark 25 Release. NAG Copyright 2014.
      .. Use Statements ..
     Use nag_library, Only: g05kff, g05tff, nag_wp, x02amf
!
      .. Implicit None Statement ..
     Implicit None
     .. Parameters ..
     Integer, Parameter
                                       :: lseed = 1, maxlr = 5000, nin = 5,
                                          nout = 6
      .. Local Scalars ..
     Real (Kind=nag_wp)
                                        :: a
     Integer
                                        :: genid, ifail, lr, lstate, mode, n,
                                           subid
      .. Local Arrays ..
     Real (Kind=nag_wp), Allocatable :: r(:)
     Integer
                                       :: seed(lseed)
     Integer, Allocatable
                                        :: state(:), x(:)
!
      .. Intrinsic Procedures ..
     Intrinsic
                                        :: int
      .. Executable Statements ..
!
     Write (nout,*) 'GO5TFF Example Program Results'
     Write (nout,*)
!
     Skip heading in data file
     Read (nin,*)
!
     Read in the base generator information and seed
     Read (nin,*) genid, subid, seed(1)
      Initial call to initialiser to get size of STATE array
      lstate = 0
     Allocate (state(lstate))
      ifail = 0
     Call g05kff(genid, subid, seed, lseed, state, lstate, ifail)
     Reallocate STATE
!
     Deallocate (state)
     Allocate (state(lstate))
     Initialize the generator to a repeatable sequence
     ifail = 0
     Call g05kff(genid, subid, seed, lseed, state, lstate, ifail)
     Read in sample size
     Read (nin,*) n
     Read in the distribution parameters
     Read (nin,*) a
```

G05TFF.4 Mark 25

```
!
      Use suggested value for LR
      If (1.0E0\_nag\_wp-a< x02amf()) Then
       A is too close to 1.0 to calculate LR, so
        set to MAXLR, which means we will use \texttt{MODE} = 3
!
        lr = maxlr
      Else
        lr = int(1.8E1_nag_wp+4.0E1_nag_wp/(1.0E0_nag_wp-a))
      End If
      lr = maxlr
      If R is a reasonable size use MODE = 2
!
!
      else do not reference R and use MODE = 3
      If (lr<maxlr) Then</pre>
       mode = 2
      Else
        mode = 3
        lr = 0
      End If
      Allocate (x(n),r(lr))
      Generate the variates
      ifail = 0
      Call g05tff(mode,n,a,r,lr,state,x,ifail)
      Display the variates
      Write (nout, 99999) x(1:n)
99999 Format (1X,I12)
    End Program g05tffe
```

### 10.2 Program Data

```
GO5TFF Example Program Data
1 1 1762543 :: GENID, SUBID, SEED(1)
10 :: N
0.9999 :: A
```

### 10.3 Program Results

```
GO5TFF Example Program Results

    6
    23
    2765
    30
    3
    1
    299
    968
    166
```

4

Mark 25 G05TFF.5 (last)