

NAG Library Routine Document

G05SAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

G05SAF generates a vector of pseudorandom numbers taken from a uniform distribution between 0 and 1.

2 Specification

```
SUBROUTINE G05SAF (N, STATE, X, IFAIL)
  INTEGER          N, STATE(*), IFAIL
  REAL (KIND=nag_wp) X(N)
```

3 Description

G05SAF generates n values from a uniform distribution over the half closed interval $(0, 1]$.

One of the initialization routines G05KFF (for a repeatable sequence if computed sequentially) or G05KGF (for a non-repeatable sequence) must be called prior to the first call to G05SAF.

4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison–Wesley

5 Parameters

- 1: N – INTEGER *Input*
On entry: n , the number of pseudorandom numbers to be generated.
Constraint: $N \geq 0$.
- 2: STATE(*) – INTEGER array *Communication Array*
Note: the actual argument supplied **must** be the array STATE supplied to the initialization routines G05KFF or G05KGF.
On entry: contains information on the selected base generator and its current state.
On exit: contains updated information on the state of the generator.
- 3: X(N) – REAL (KIND=nag_wp) array *Output*
On exit: the n pseudorandom numbers from a uniform distribution over the half closed interval $(0, 1]$.
- 4: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the

recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1 , explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, $N = \langle value \rangle$.
Constraint: $N \geq 0$.

IFAIL = 2

On entry, STATE vector has been corrupted or not initialized.

IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.
See Section 3.8 in the Essential Introduction for further information.

IFAIL = -399

Your licence key may have expired or may not have been installed correctly.
See Section 3.7 in the Essential Introduction for further information.

IFAIL = -999

Dynamic memory allocation failed.
See Section 3.6 in the Essential Introduction for further information.

7 Accuracy

Not applicable.

8 Parallelism and Performance

G05SAF is threaded by NAG for parallel execution in multithreaded implementations of the NAG Library.

Please consult the X06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this routine. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

9 Further Comments

None.

10 Example

This example prints the first five pseudorandom numbers from a uniform distribution between 0 and 1, generated by G05SAF after initialization by G05KFF.

10.1 Program Text

```

Program g05safe

!      G05SAF Example Program Text

!      Mark 25 Release. NAG Copyright 2014.

!      .. Use Statements ..
Use nag_library, Only: g05kff, g05saf, nag_wp
!      .. Implicit None Statement ..
Implicit None
!      .. Parameters ..
Integer, Parameter          :: lseed = 1, nin = 5, nout = 6
!      .. Local Scalars ..
Integer                    :: genid, ifail, lstate, n, subid
!      .. Local Arrays ..
Real (Kind=nag_wp), Allocatable :: x(:)
Integer                    :: seed(lseed)
Integer, Allocatable       :: state(:)
!      .. Executable Statements ..
Write (nout,*) 'G05SAF Example Program Results'
Write (nout,*)

!      Skip heading in data file
Read (nin,*)

!      Read in the base generator information and seed
Read (nin,*) genid, subid, seed(1)

!      Initial call to initialiser to get size of STATE array
lstate = 0
Allocate (state(lstate))
ifail = 0
Call g05kff(genid,subid,seed,lseed,state,lstate,ifail)

!      Reallocate STATE
Deallocate (state)
Allocate (state(lstate))

!      Initialize the generator to a repeatable sequence
ifail = 0
Call g05kff(genid,subid,seed,lseed,state,lstate,ifail)

!      Read in sample size
Read (nin,*) n

Allocate (x(n))

!      Generate the variates
ifail = 0
Call g05saf(n,state,x,ifail)

!      Display the variates
Write (nout,99999) x(1:n)

99999 Format (1X,F10.4)
End Program g05safe

```

10.2 Program Data

```

G05SAF Example Program Data
1 1 1762543      :: GENID,SUBID,SEED(1)
5              :: N

```

10.3 Program Results

G05SAF Example Program Results

0.6364
0.1065
0.7460
0.7983
0.1046
