

NAG Library Function Document

nag_rand_basic (g05sac)

1 Purpose

nag_rand_basic (g05sac) generates a vector of pseudorandom numbers taken from a uniform distribution between 0 and 1.

2 Specification

```
#include <nag.h>
#include <nagg05.h>
void nag_rand_basic (Integer n, Integer state[], double x[], NagError *fail)
```

3 Description

nag_rand_basic (g05sac) generates n values from a uniform distribution over the half closed interval $(0, 1]$.

One of the initialization functions nag_rand_init_repeatable (g05kfc) (for a repeatable sequence if computed sequentially) or nag_rand_init_nonrepeatable (g05kgc) (for a non-repeatable sequence) must be called prior to the first call to nag_rand_basic (g05sac).

4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison–Wesley

5 Arguments

- 1: **n** – Integer *Input*
On entry: n , the number of pseudorandom numbers to be generated.
Constraint: $n \geq 0$.
- 2: **state**[*dim*] – Integer *Communication Array*
Note: the dimension, *dim*, of this array is dictated by the requirements of associated functions that must have been previously called. This array **MUST** be the same array passed as argument **state** in the previous call to nag_rand_init_repeatable (g05kfc) or nag_rand_init_nonrepeatable (g05kgc).
On entry: contains information on the selected base generator and its current state.
On exit: contains updated information on the state of the generator.
- 3: **x**[**n**] – double *Output*
On exit: the n pseudorandom numbers from a uniform distribution over the half closed interval $(0, 1]$.
- 4: **fail** – NagError * *Input/Output*
The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.

See Section 3.2.1.2 in How to Use the NAG Library and its Documentation for further information.

NE_BAD_PARAM

On entry, argument $\langle value \rangle$ had an illegal value.

NE_INT

On entry, $n = \langle value \rangle$.

Constraint: $n \geq 0$.

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please contact NAG for assistance.

An unexpected error has been triggered by this function. Please contact NAG.

See Section 3.6.6 in How to Use the NAG Library and its Documentation for further information.

NE_INVALID_STATE

On entry, **state** vector has been corrupted or not initialized.

NE_NO_LICENCE

Your licence key may have expired or may not have been installed correctly.

See Section 3.6.5 in How to Use the NAG Library and its Documentation for further information.

7 Accuracy

Not applicable.

8 Parallelism and Performance

`nag_rand_basic` (g05sac) is threaded by NAG for parallel execution in multithreaded implementations of the NAG Library.

Please consult the x06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this function. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

9 Further Comments

None.

10 Example

This example prints the first five pseudorandom numbers from a uniform distribution between 0 and 1, generated by `nag_rand_basic` (g05sac) after initialization by `nag_rand_init_repeatabl` (g05kfc).

10.1 Program Text

```

/* nag_rand_basic (g05sac) Example Program.
 *
 * NAGPRODCODE Version.
 *
 * Copyright 2016 Numerical Algorithms Group.
 *
 * Mark 26, 2016.
 */
/* Pre-processor includes */
#include <stdio.h>
#include <math.h>
#include <nag.h>
#include <nag_stdlib.h>
#include <nagg05.h>

int main(void)
{
    /* Integer scalar and array declarations */
    Integer exit_status = 0;
    Integer i, lstate;
    Integer *state = 0;

    /* NAG structures */
    NagError fail;

    /* Double scalar and array declarations */
    double *x = 0;

    /* Set the sample size */
    Integer n = 5;

    /* Choose the base generator */
    Nag_BaseRNG genid = Nag_Basic;
    Integer subid = 0;

    /* Set the seed */
    Integer seed[] = { 1762543 };
    Integer lseed = 1;

    /* Initialize the error structure */
    INIT_FAIL(fail);

    printf("nag_rand_basic (g05sac) Example Program Results\n\n");

    /* Get the length of the state array */
    lstate = -1;
    nag_rand_init_repeatable(genid, subid, seed, lseed, state, &lstate, &fail);
    if (fail.code != NE_NOERROR) {
        printf("Error from nag_rand_init_repeatable (g05kfc).\n%s\n",
            fail.message);
        exit_status = 1;
        goto END;
    }

    /* Allocate arrays */
    if (!(x = NAG_ALLOC(n, double)) || !(state = NAG_ALLOC(lstate, Integer)))
    {
        printf("Allocation failure\n");
        exit_status = -1;
        goto END;
    }

    /* Initialize the generator to a repeatable sequence */
    nag_rand_init_repeatable(genid, subid, seed, lseed, state, &lstate, &fail);
    if (fail.code != NE_NOERROR) {
        printf("Error from nag_rand_init_repeatable (g05kfc).\n%s\n",
            fail.message);
        exit_status = 1;
        goto END;
    }
}

```

```
    }

    /* Generate the variates */
    nag_rand_basic(n, state, x, &fail);
    if (fail.code != NE_NOERROR) {
        printf("Error from nag_rand_basic (g05sac).\n%s\n", fail.message);
        exit_status = 1;
        goto END;
    }

    /* Display the variates */
    for (i = 0; i < n; i++) {
        printf("%10.4f\n", x[i]);
    }

END:
    NAG_FREE(x);
    NAG_FREE(state);

    return exit_status;
}
```

10.2 Program Data

None.

10.3 Program Results

nag_rand_basic (g05sac) Example Program Results

```
0.6364
0.1065
0.7460
0.7983
0.1046
```
