NAG Library Routine Document

G02HLF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

G02HLF calculates a robust estimate of the covariance matrix for user-supplied weight functions and their derivatives.

2 Specification

3 Description

For a set of n observations on m variables in a matrix X, a robust estimate of the covariance matrix, C, and a robust estimate of location, θ , are given by:

$$C = \tau^2 (A^{\mathsf{T}} A)^{-1},$$

where τ^2 is a correction factor and A is a lower triangular matrix found as the solution to the following equations.

$$z_i = A(x_i - \theta)$$

$$\frac{1}{n}\sum_{i=1}^{n}w(\|z_{i}\|_{2})z_{i}=0$$

and

$$\frac{1}{n} \sum_{i=1}^{n} u(\|z_i\|_2) z_i z_i^{\mathsf{T}} - v(\|z_i\|_2) I = 0,$$

where x_i is a vector of length m containing the elements of the ith row of X,

 z_i is a vector of length m,

I is the identity matrix and 0 is the zero matrix,

and w and u are suitable functions.

G02HLF covers two situations:

- (i) v(t) = 1 for all t,
- (ii) v(t) = u(t).

The robust covariance matrix may be calculated from a weighted sum of squares and cross-products matrix about θ using weights $wt_i = u(||z_i||)$. In case (i) a divisor of n is used and in case (ii) a divisor of $\sum_{i=1}^{n} wt_i$

is used. If $w(.) = \sqrt{u(.)}$, then the robust covariance matrix can be calculated by scaling each row of X by $\sqrt{wt_i}$ and calculating an unweighted covariance matrix about θ .

In order to make the estimate asymptotically unbiased under a Normal model a correction factor, τ^2 , is needed. The value of the correction factor will depend on the functions employed (see Huber (1981) and Marazzi (1987)).

G02HLF finds A using the iterative procedure as given by Huber.

$$A_k = (S_k + I)A_{k-1}$$

and

$$\theta_{j_k} = \frac{b_j}{D_1} + \theta_{j_{k-1}},$$

where $S_k = (s_{jl})$, for j = 1, 2, ..., m and l = 1, 2, ..., m, is a lower triangular matrix such that:

$$s_{jl} = \begin{cases} -\min\bigl[\max\bigl(h_{jl}/D_3, -BL\bigr), BL\bigr], & j > l \\ -\min\bigl[\max\bigl\bigl(\bigl(h_{jj}/(2D_3 - D_4/D_2)\bigr), -BD\bigr), BD\bigr], & j = l \end{cases},$$

where

$$D_{1} = \sum_{i=1}^{n} \left\{ w(\|z_{i}\|_{2}) + \frac{1}{m} w'(\|z_{i}\|_{2}) \|z_{i}\|_{2} \right\}$$

$$D_{2} = \sum_{i=1}^{n} \left\{ \frac{1}{p} (u'(\|z_{i}\|_{2}) \|z_{i}\|_{2} + 2u(\|z_{i}\|_{2})) \|z_{i}\|_{2} - v'(\|z_{i}\|_{2}) \right\} \|z_{i}\|_{2}$$

$$D_{3} = \frac{1}{m+2} \sum_{i=1}^{n} \left\{ \frac{1}{m} (u'(\|z_{i}\|_{2}) \|z_{i}\|_{2} + 2u(\|z_{i}\|_{2})) + u(\|z_{i}\|_{2}) \right\} \|z_{i}\|_{2}^{2}$$

$$D_{4} = \sum_{i=1}^{n} \left\{ \frac{1}{m} u(\|z_{i}\|_{2}) \|z_{i}\|_{2}^{2} - v(\|z_{i}\|_{2}^{2}) \right\}$$

$$h_{jl} = \sum_{i=1}^{n} u(\|z_{i}\|_{2}) z_{ij} z_{il}, \text{ for } j > l$$

$$h_{jj} = \sum_{i=1}^{n} u(\|z_{i}\|_{2}) \left(z_{ij}^{2} - \|z_{ij}\|_{2}^{2} / m\right)$$

$$b_{j} = \sum_{i=1}^{n} w(\|z_{i}\|_{2}) (x_{ij} - b_{j})$$

and BD and BL are suitable bounds.

G02HLF is based on routines in ROBETH; see Marazzi (1987).

4 References

Huber P J (1981) Robust Statistics Wiley

Marazzi A (1987) Weights for bounded influence regression in ROBETH Cah. Rech. Doc. IUMSP, No. 3 ROB 3 Institut Universitaire de Médecine Sociale et Préventive, Lausanne

5 Parameters

1: UCV – SUBROUTINE, supplied by the user. External Procedure UCV must return the values of the functions u and w and their derivatives for a given value of its argument.

G02HLF.2 Mark 24

The specification of UCV is:

SUBROUTINE UCV (T, RUSER, U, UD, W, WD)

REAL (KIND=nag_wp) T, RUSER(*), U, UD, W, WD

1: T - REAL (KIND=nag wp)

Input

On entry: the argument for which the functions u and w must be evaluated.

2: RUSER(*) – REAL (KIND=nag_wp) array

User Workspace

UCV is called with the parameter RUSER as supplied to G02HLF. You are free to use the array RUSER to supply information to UCV as an alternative to using COMMON global variables.

3: $U - REAL (KIND=nag_wp)$

Output

On exit: the value of the u function at the point T.

Constraint: $U \ge 0.0$.

4: UD – REAL (KIND=nag wp)

Output

On exit: the value of the derivative of the u function at the point T.

5: $W - REAL (KIND=nag_wp)$

Output

On exit: the value of the w function at the point T.

Constraint: $W \ge 0.0$.

6: WD - REAL (KIND=nag wp)

Output

On exit: the value of the derivative of the w function at the point T.

UCV must either be a module subprogram USEd by, or declared as EXTERNAL in, the (sub)program from which G02HLF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

2: RUSER(*) - REAL (KIND=nag_wp) array

User Workspace

RUSER is not used by G02HLF, but is passed directly to UCV and may be used to pass information to this routine as an alternative to using COMMON global variables.

3: INDM – INTEGER

Input

On entry: indicates which form of the function v will be used.

INDM = 1

v = 1.

 $INDM \neq 1$

v = u.

4: N - INTEGER

Input

On entry: n, the number of observations.

Constraint: N > 1.

5: M – INTEGER

Input

On entry: m, the number of columns of the matrix X, i.e., number of independent variables.

Constraint: $1 \le M \le N$.

G02HLF NAG Library Manual

6: $X(LDX,M) - REAL (KIND=nag_wp) array$

Input

On entry: X(i, j) must contain the *i*th observation on the *j*th variable, for i = 1, 2, ..., n and j = 1, 2, ..., m.

7: LDX – INTEGER

Input

On entry: the first dimension of the array X as declared in the (sub)program from which G02HLF is called.

Constraint: LDX \geq N.

8: $COV(M \times (M+1)/2) - REAL$ (KIND=nag wp) array

Output

On exit: contains a robust estimate of the covariance matrix, C. The upper triangular part of the matrix C is stored packed by columns (lower triangular stored by rows), C_{ij} is returned in $COV((j \times (j-1)/2 + i))$, $i \le j$.

9: $A(M \times (M+1)/2) - REAL$ (KIND=nag wp) array

Input/Output

On entry: an initial estimate of the lower triangular real matrix A. Only the lower triangular elements must be given and these should be stored row-wise in the array.

The diagonal elements must be $\neq 0$, and in practice will usually be > 0. If the magnitudes of the columns of X are of the same order, the identity matrix will often provide a suitable initial value for A. If the columns of X are of different magnitudes, the diagonal elements of the initial value of A should be approximately inversely proportional to the magnitude of the columns of X.

Constraint: $A(j \times (j-1)/2 + j) \neq 0.0$, for j = 1, 2, ..., m.

On exit: the lower triangular elements of the inverse of the matrix A, stored row-wise.

10: WT(N) - REAL (KIND=nag_wp) array

Output

On exit: WT(i) contains the weights, $wt_i = u(||z_i||_2)$, for i = 1, 2, ..., n.

11: THETA(M) – REAL (KIND=nag wp) array

Input/Output

On entry: an initial estimate of the location parameter, θ_j , for j = 1, 2, ..., m.

In many cases an initial estimate of $\theta_j = 0$, for j = 1, 2, ..., m, will be adequate. Alternatively medians may be used as given by G07DAF.

On exit: contains the robust estimate of the location parameter, θ_i , for i = 1, 2, ..., m.

12: BL – REAL (KIND=nag wp)

Input

On entry: the magnitude of the bound for the off-diagonal elements of S_k , BL.

Suggested value: BL = 0.9.

Constraint: BL > 0.0.

13: BD - REAL (KIND=nag_wp)

Input

On entry: the magnitude of the bound for the diagonal elements of S_k , BD.

Suggested value: BD = 0.9.

Constraint: BD > 0.0.

14: MAXIT – INTEGER

Input

On entry: the maximum number of iterations that will be used during the calculation of A.

Suggested value: MAXIT = 150.

Constraint: MAXIT > 0.

G02HLF.4 Mark 24

15: NITMON – INTEGER

Input

On entry: indicates the amount of information on the iteration that is printed.

NITMON > 0

The value of A, θ and δ (see Section 7) will be printed at the first and every NITMON iterations.

NITMON < 0

No iteration monitoring is printed.

When printing occurs the output is directed to the current advisory message unit (see X04ABF).

16: TOL – REAL (KIND=nag wp)

Input

On entry: the relative precision for the final estimates of the covariance matrix. Iteration will stop when maximum δ (see Section 7) is less than TOL.

Constraint: TOL > 0.0.

17: NIT – INTEGER

Output

On exit: the number of iterations performed.

18: $WK(2 \times M) - REAL (KIND=nag_wp) array$

Workspace

19: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
IFAIL = 1
```

```
 \begin{array}{lll} \text{On entry,} & N \leq 1, \\ \text{or} & M < 1, \\ \text{or} & N < M, \\ \text{or} & LDX < N. \end{array}
```

IFAIL = 2

```
\begin{array}{lll} \text{On entry,} & \text{TOL} \leq 0.0, \\ \text{or} & \text{MAXIT} \leq 0, \\ \text{or} & \text{diagonal element of } A = 0.0, \\ \text{or} & \text{BL} \leq 0.0, \\ \text{or} & \text{BD} \leq 0.0. \end{array}
```

IFAIL = 3

A column of X has a constant value.

```
IFAIL = 4
```

Value of U or W returned by UCV < 0.

IFAIL = 5

The routine has failed to converge in MAXIT iterations.

IFAIL = 6

One of the following is zero: D_1 , D_2 or D_3 .

This may be caused by the functions u or w being too strict for the current estimate of A (or C). You should try either a larger initial estimate of A or make u and w less strict.

7 Accuracy

On successful exit the accuracy of the results is related to the value of TOL; see Section 5. At an iteration let

- (i) d1 = the maximum value of $|s_{il}|$
- (ii) d2 = the maximum absolute change in wt(i)
- (iii) d3 = the maximum absolute relative change in θ_i

and let $\delta = \max(d1, d2, d3)$. Then the iterative procedure is assumed to have converged when $\delta < \text{TOL}$.

8 Further Comments

The existence of A will depend upon the function u (see Marazzi (1987)); also if X is not of full rank a value of A will not be found. If the columns of X are almost linearly related, then convergence will be slow.

9 Example

A sample of 10 observations on three variables is read in along with initial values for A and THETA and parameter values for the u and w functions, c_u and c_w . The covariance matrix computed by G02HLF is printed along with the robust estimate of θ . UCV computes the Huber's weight functions:

$$u(t) = 1$$
, if $t \le c_u^2$

$$u(t) = \frac{c_u}{t^2}$$
, if $t > c_u^2$

and

$$w(t) = 1$$
, if $t \le c_w$

$$w(t) = \frac{c_w}{t}$$
, if $t > c_w$

and their derivatives.

9.1 Program Text

G02HLF.6 Mark 24

```
!
      .. Implicit None Statement ..
     Implicit None
!
      .. Parameters ..
      Integer, Parameter
                                             :: iset = 1, nin = 5, nout = 6
    Contains
      Subroutine ucv(t,ruser,u,ud,w,wd)
        u function and derivative
        .. Scalar Arguments ..
!
        Real (Kind=nag_wp), Intent (In)
        Real (Kind=nag_wp), Intent (Out)
                                               :: u, ud, w, wd
        .. Array Arguments .. Real (Kind=nag_wp), Intent (Inout)
!
                                               :: ruser(*)
!
        .. Local Scalars ..
        Real (Kind=nag_wp)
                                                :: cu, cw, t2
        .. Executable Statements ..
        cu = ruser(1)
        u = 1.0_nag_wp
        ud = 0.0_nag_wp
        If (t/=0.0_nag_wp) Then
          t2 = t*t
          If (t2>cu) Then
            u = cu/t2
            ud = -2.0_nag_wp*u/t
          End If
        End If
        w function and derivative
        cw = ruser(2)
        If (t>cw) Then
          w = cw/t
          wd = -w/t
        Else
          w = 1.0_nag_wp
          wd = 0.0 \underline{nag} \underline{wp}
        End If
      End Subroutine ucv
    End Module g02hlfe_mod
    Program g02hlfe
!
      GO2HLF Example Main Program
!
      .. Use Statements ..
      Use nag_library, Only: g02hlf, nag_wp, x04abf, x04ccf Use g02hlfe_mod, Only: iset, nin, nout, ucv
      .. Implicit None Statement ..
!
      Implicit None
!
      .. Local Scalars ..
                                              :: bd, bl, tol
      Real (Kind=nag_wp)
                                              :: i, ifail, indm, la, lcov, ldx, &
      Integer
                                                 lruser, m, maxit, n, nadv, nit, &
                                                 nitmon
      .. Local Arrays ..
      Real (Kind=nag_wp), Allocatable
                                              :: a(:), cov(:), ruser(:),
                                                 theta(:), wk(:), wt(:), x(:,:)
      .. Executable Statements ..
      Write (nout,*) 'GO2HLF Example Program Results'
      Write (nout,*)
      Skip heading in data file
!
      Read (nin,*)
!
      Read in the problem size
      Read (nin,*) n, m
      ldx = n
      lruser = 2
      la = (m+1)*m/2
      lcov = la
      Allocate (x(ldx,m),ruser(lruser),cov(lcov),a(la),wt(n),theta(m),wk(2*m))
```

G02HLF NAG Library Manual

```
Read in the data
      Read (nin,*)(x(i,1:m),i=1,n)
      Read in the initial value of A
      Read (nin,*) a(1:la)
      Read in the initial value of THETA
      Read (nin,*) theta(1:m)
!
      Read in the values of the parameters of the ucv functions
      Read (nin,*) ruser(1:lruser)
      Read in the control parameters
      Read (nin,*) indm, nitmon, bl, bd, maxit, tol
      Set the advisory channel to NOUT for monitoring information
      If (nitmon/=0) Then
        nadv = nout
        Call x04abf(iset,nadv)
      End If
      Compute robust estimate of variance / covariance matrix
      ifail = 0
      Call gO2hlf(ucv,ruser,indm,n,m,x,ldx,cov,a,wt,theta,bl,bd,maxit,nitmon, &
        tol, nit, wk, ifail)
!
      Display results
      Write (nout, 99999) 'GO2HLF required ', nit, ' iterations to converge'
      Write (nout,*)
      Flush (nout)
      ifail = 0
      Call x04ccf('Upper','Non-Unit',m,cov,'Robust covariance matrix',ifail)
      Write (nout,*)
      Write (nout,*) 'Robust estimates of THETA'
      Write (nout,99998) theta(1:m)
99999 Format (1X,A,IO,A)
99998 Format (1X,F10.3)
    End Program g02hlfe
9.2 Program Data
GO2HLF Example Program Data
   10 3
                               : N, M
  3.4 6.9 12.2
 6.4 2.5 15.1
4.9 5.5 14.2
7.3 1.9 18.2
  8.8 3.6 11.7
  8.4 1.3 17.9
5.3 3.1 15.0
2.7 8.1 7.7
  6.1 3.0 21.9
  5.3 2.2 13.9
                              : End of X
  1.0 0.0 1.0 0.0 0.0 1.0
                              : A
  0.0 0.0 0.0
                               : THETA
                               : RUSER
  4.0 2.0
1 0 0.9 0.9 50 5.0E-5
                              : INDM, NITMON, BL, BD, MAXIT, TOL
9.3 Program Results
 GO2HLF Example Program Results
 GO2HLF required 25 iterations to converge
 Robust covariance matrix
                                    3
             1
                         2
 1
        3.2778
                  -3.6918
                              4.7391
 2
                    5.2841
                              -6.4086
                              11.8371
 3
```

G02HLF.8 Mark 24

Robust estimates of THETA 5.700 3.864

14.704

Mark 24 G02HLF.9 (last)