

NAG Library Function Document

nag_rand_weibull (g05ssc)

1 Purpose

nag_rand_weibull (g05ssc) generates a vector of pseudorandom numbers from a two parameter Weibull distribution with shape parameter a and scale parameter b .

2 Specification

```
#include <nag.h>
#include <nagg05.h>

void nag_rand_weibull (Integer n, double a, double b, Integer state[],
                      double x[], NagError *fail)
```

3 Description

The distribution has PDF (probability density function)

$$f(x) = \frac{a}{b} x^{a-1} e^{-x^a/b} \quad \text{if } x > 0,$$

$$f(x) = 0 \quad \text{otherwise.}$$

nag_rand_weibull (g05ssc) returns the value $(-b \ln y)^{1/a}$, where y is a pseudorandom number from a uniform distribution over $(0, 1]$.

One of the initialization functions nag_rand_init_repeatable (g05kfc) (for a repeatable sequence if computed sequentially) or nag_rand_init_nonrepeatable (g05kgc) (for a non-repeatable sequence) must be called prior to the first call to nag_rand_weibull (g05ssc).

4 References

Kendall M G and Stuart A (1969) *The Advanced Theory of Statistics (Volume 1)* (3rd Edition) Griffin
 Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison–Wesley

5 Arguments

- | | | |
|----|--|--------------|
| 1: | n – Integer | <i>Input</i> |
| | <i>On entry:</i> n , the number of pseudorandom numbers to be generated. | |
| | <i>Constraint:</i> $n \geq 0$. | |
| 2: | a – double | <i>Input</i> |
| | <i>On entry:</i> a , the shape parameter of the distribution. | |
| | <i>Constraint:</i> $a > 0.0$. | |
| 3: | b – double | <i>Input</i> |
| | <i>On entry:</i> b , the scale parameter of the distribution. | |
| | <i>Constraint:</i> $b > 0.0$. | |

- 4: **state** $[dim]$ – Integer *Communication Array*
Note: the dimension, *dim*, of this array is dictated by the requirements of associated functions that must have been previously called. This array **MUST** be the same array passed as argument **state** in the previous call to `nag_rand_init_repeatable` (g05kfc) or `nag_rand_init_nonrepeatable` (g05kge).
On entry: contains information on the selected base generator and its current state.
On exit: contains updated information on the state of the generator.
- 5: **x** $[n]$ – double *Output*
On exit: the *n* pseudorandom numbers from the specified Weibull distribution.
- 6: **fail** – NagError * *Input/Output*
The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.

See Section 2.3.1.2 in How to Use the NAG Library and its Documentation for further information.

NE_BAD_PARAM

On entry, argument $\langle value \rangle$ had an illegal value.

NE_INT

On entry, $n = \langle value \rangle$.

Constraint: $n \geq 0$.

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please contact NAG for assistance.

An unexpected error has been triggered by this function. Please contact NAG.

See Section 2.7.6 in How to Use the NAG Library and its Documentation for further information.

NE_INVALID_STATE

On entry, **state** vector has been corrupted or not initialized.

NE_NO_LICENCE

Your licence key may have expired or may not have been installed correctly.

See Section 2.7.5 in How to Use the NAG Library and its Documentation for further information.

NE_REAL

On entry, $a = \langle value \rangle$.

Constraint: $a > 0.0$.

On entry, $b = \langle value \rangle$.

Constraint: $b > 0.0$.

7 Accuracy

Not applicable.

8 Parallelism and Performance

nag_rand_weibull (g05ssc) is threaded by NAG for parallel execution in multithreaded implementations of the NAG Library.

Please consult the x06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this function. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

9 Further Comments

None.

10 Example

This example prints the first five pseudorandom numbers from a Weibull distribution with shape parameter 1.0 and scale parameter 2.0, generated by a single call to nag_rand_weibull (g05ssc), after initialization by nag_rand_init_repeatable (g05kfc).

10.1 Program Text

```

/* nag_rand_weibull (g05ssc) Example Program.
 *
 * NAGPRODCODE Version.
 *
 * Copyright 2016 Numerical Algorithms Group.
 *
 * Mark 26, 2016.
 */
/* Pre-processor includes */
#include <stdio.h>
#include <math.h>
#include <nag.h>
#include <nag_stdlib.h>
#include <nagg05.h>

int main(void)
{
    /* Integer scalar and array declarations */
    Integer exit_status = 0;
    Integer i, lstate;
    Integer *state = 0;

    /* NAG structures */
    NagError fail;

    /* Double scalar and array declarations */
    double *x = 0;

    /* Set the distribution parameters */
    double a = 1.0e0;
    double b = 2.0e0;

    /* Set the sample size */
    Integer n = 5;

    /* Choose the base generator */
    Nag_BaseRNG genid = Nag_Basic;
    Integer subid = 0;

    /* Set the seed */
    Integer seed[] = { 1762543 };

```

```

Integer lseed = 1;

/* Initialize the error structure */
INIT_FAIL(fail);

printf("nag_rand_weibull (g05ssc) Example Program Results\n\n");

/* Get the length of the state array */
lstate = -1;
nag_rand_init_repeatabe(genid, subid, seed, lseed, state, &lstate, &fail);
if (fail.code != NE_NOERROR) {
    printf("Error from nag_rand_init_repeatabe (g05kfc).\n%s\n",
        fail.message);
    exit_status = 1;
    goto END;
}

/* Allocate arrays */
if (!(x = NAG_ALLOC(n, double)) || !(state = NAG_ALLOC(lstate, Integer)))
{
    printf("Allocation failure\n");
    exit_status = -1;
    goto END;
}

/* Initialize the generator to a repeatable sequence */
nag_rand_init_repeatabe(genid, subid, seed, lseed, state, &lstate, &fail);
if (fail.code != NE_NOERROR) {
    printf("Error from nag_rand_init_repeatabe (g05kfc).\n%s\n",
        fail.message);
    exit_status = 1;
    goto END;
}

/* Generate the variates */
nag_rand_weibull(n, a, b, state, x, &fail);
if (fail.code != NE_NOERROR) {
    printf("Error from nag_rand_weibull (g05ssc).\n%s\n", fail.message);
    exit_status = 1;
    goto END;
}

/* Display the variates */
for (i = 0; i < n; i++)
    printf("%10.4f\n", x[i]);

END:
    NAG_FREE(x);
    NAG_FREE(state);

    return exit_status;
}

```

10.2 Program Data

None.

10.3 Program Results

nag_rand_weibull (g05ssc) Example Program Results

```

0.9039
4.4796
0.5860
0.4506
4.5154

```
