

NAG Library Routine Document

F06UJF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F06UJF returns, via the function name, the value of the 1-norm, the ∞ -norm, the Frobenius norm, or the maximum absolute value of the elements of a complex m by n trapezoidal matrix (triangular if $m = n$).

2 Specification

```
FUNCTION F06UJF (NORM, UPLO, DIAG, M, N, A, LDA, WORK)
REAL (KIND=nag_wp) F06UJF
INTEGER                M, N, LDA
REAL (KIND=nag_wp)    WORK(*)
COMPLEX (KIND=nag_wp) A(LDA,*)
CHARACTER(1)          NORM, UPLO, DIAG
```

3 Description

None.

4 References

None.

5 Arguments

- 1: NORM – CHARACTER(1) *Input*
On entry: specifies the value to be returned.
 NORM = '1' or 'O'
 The 1-norm.
 NORM = 'I'
 The ∞ -norm.
 NORM = 'F' or 'E'
 The Frobenius (or Euclidean) norm.
 NORM = 'M'
 The value $\max_{i,j} |a_{ij}|$ (not a norm).
Constraint: NORM = '1', 'O', 'I', 'F', 'E' or 'M'.
- 2: UPLO – CHARACTER(1) *Input*
On entry: specifies whether A is upper or lower trapezoidal.
 UPLO = 'U'
 A is upper trapezoidal.
 UPLO = 'L'
 A is lower trapezoidal.
Constraint: UPLO = 'U' or 'L'.

- 3: DIAG – CHARACTER(1) *Input*
On entry: specifies whether A has nonunit or unit diagonal elements.
 DIAG = 'N'
 The diagonal elements are stored explicitly.
 DIAG = 'U'
 The diagonal elements are assumed to be 1, and are not referenced.
Constraint: DIAG = 'N' or 'U'.
- 4: M – INTEGER *Input*
On entry: m , the number of rows of the matrix A .
 When $M = 0$, F06UJF is set to zero.
Constraint: $M \geq 0$.
- 5: N – INTEGER *Input*
On entry: n , the number of columns of the matrix A .
 When $N = 0$, F06UJF is set to zero.
Constraint: $N \geq 0$.
- 6: A(LDA,*) – COMPLEX (KIND=nag_wp) array *Input*
Note: the second dimension of the array A must be at least N .
On entry: the m by n trapezoidal matrix A .
 If UPLO = 'U', A is upper trapezoidal and the elements of the array below the diagonal are not referenced.
 If UPLO = 'L', A is lower trapezoidal and the elements of the array above the diagonal are not referenced.
 If DIAG = 'U', the diagonal elements of A are assumed to be 1, and are not referenced.
- 7: LDA – INTEGER *Input*
On entry: the first dimension of the array A as declared in the (sub)program from which F06UJF is called.
Constraint: $LDA \geq \max(1, M)$.
- 8: WORK(*) – REAL (KIND=nag_wp) array *Workspace*
Note: the dimension of the array WORK must be at least $\max(1, M)$ if NORM = 'I', and at least 1 otherwise.

6 Error Indicators and Warnings

None.

7 Accuracy

Not applicable.

8 Parallelism and Performance

F06UJF is not threaded in any implementation.

9 Further Comments

None.

10 Example

None.
