

NAG Library Routine Document

G03CAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

G03CAF computes the maximum likelihood estimates of the arguments of a factor analysis model. Either the data matrix or a correlation/covariance matrix may be input. Factor loadings, communalities and residual correlations are returned.

2 Specification

```

SUBROUTINE G03CAF (MATRIX, WEIGHT, N, M, X, LDX, NVAR, ISX, NFAC, WT, E, &
                  STAT, COM, PSI, RES, FL, LDFL, IOP, IWK, WK, LWK, &
                  IFAIL)
INTEGER          N, M, LDX, NVAR, ISX(M), NFAC, LDFL, IOP(5), &
                IWK(4*NVAR+2), LWK, IFAIL
REAL (KIND=nag_wp) X(LDX,M), WT(*), E(NVAR), STAT(4), COM(NVAR), &
                  PSI(NVAR), RES(NVAR*(NVAR-1)/2), FL(LDFL,NFAC), &
                  WK(LWK)
CHARACTER(1)    MATRIX, WEIGHT

```

3 Description

Let p variables, x_1, x_2, \dots, x_p , with variance-covariance matrix Σ be observed. The aim of factor analysis is to account for the covariances in these p variables in terms of a smaller number, k , of hypothetical variables, or factors, f_1, f_2, \dots, f_k . These are assumed to be independent and to have unit variance. The relationship between the observed variables and the factors is given by the model:

$$x_i = \sum_{j=1}^k \lambda_{ij} f_j + e_i, \quad i = 1, 2, \dots, p$$

where λ_{ij} , for $i = 1, 2, \dots, p$ and $j = 1, 2, \dots, k$, are the factor loadings and e_i , for $i = 1, 2, \dots, p$, are independent random variables with variances ψ_i , for $i = 1, 2, \dots, p$. The ψ_i represent the unique component of the variation of each observed variable. The proportion of variation for each variable accounted for by the factors is known as the communality. For this routine it is assumed that both the k factors and the e_i 's follow independent Normal distributions.

The model for the variance-covariance matrix, Σ , can be written as:

$$\Sigma = \Lambda \Lambda^T + \Psi \quad (1)$$

where Λ is the matrix of the factor loadings, λ_{ij} , and Ψ is a diagonal matrix of unique variances, ψ_i , for $i = 1, 2, \dots, p$.

The estimation of the arguments of the model, Λ and Ψ , by maximum likelihood is described by Lawley and Maxwell (1971). The log-likelihood is:

$$-\frac{1}{2}(n-1)\log(|S|) - \frac{1}{2}(n-1)\text{trace}(S, \Sigma^{-1}) + \text{constant},$$

where n is the number of observations, S is the sample variance-covariance matrix or, if weights are used, S is the weighted sample variance-covariance matrix and n is the effective number of observations, that is, the sum of the weights. The constant is independent of the arguments of the model. A two stage maximization is employed. It makes use of the function $F(\Psi)$, which is, up to a constant, $-2/(n-1)$ times the log-likelihood maximized over Λ . This is then minimized with respect to Ψ to give the estimates, $\hat{\Psi}$, of Ψ . The function $F(\Psi)$ can be written as:

$$F(\Psi) = \sum_{j=k+1}^p (\theta_j - \log \theta_j) - (p - k)$$

where values θ_j , for $j = 1, 2, \dots, p$ are the eigenvalues of the matrix:

$$S^* = \Psi^{-1/2} S \Psi^{-1/2}.$$

The estimates $\hat{\Lambda}$, of Λ , are then given by scaling the eigenvectors of S^* , which are denoted by V :

$$\hat{\Lambda} = \Psi^{1/2} V(\Theta - I)^{1/2}.$$

where Θ is the diagonal matrix with elements θ_i , and I is the identity matrix.

The minimization of $F(\Psi)$ is performed using E04LBF which uses a modified Newton algorithm. The computation of the Hessian matrix is described by Clark (1970). However, instead of using the eigenvalue decomposition of the matrix S^* as described above, the singular value decomposition of the matrix $R\Psi^{-1/2}$ is used, where R is obtained either from the QR decomposition of the (scaled) mean centred data matrix or from the Cholesky decomposition of the correlation/covariance matrix. The routine E04LBF ensures that the values of ψ_i are greater than a given small positive quantity, δ , so that the communality is always less than one. This avoids the so called Heywood cases.

In addition to the values of Λ , Ψ and the communalities, G03CAF returns the residual correlations, i.e., the off-diagonal elements of $C - (\Lambda\Lambda^T + \Psi)$ where C is the sample correlation matrix. G03CAF also returns the test statistic:

$$\chi^2 = [n - 1 - (2p + 5)/6 - 2k/3]F(\hat{\Psi})$$

which can be used to test the goodness-of-fit of the model (1), see Lawley and Maxwell (1971) and Morrison (1967).

4 References

Clark M R B (1970) A rapidly convergent method for maximum likelihood factor analysis *British J. Math. Statist. Psych.*

Hammarling S (1985) The singular value decomposition in multivariate statistics *SIGNUM Newsl.* **20(3)** 2–25

Lawley D N and Maxwell A E (1971) *Factor Analysis as a Statistical Method* (2nd Edition) Butterworths

Morrison D F (1967) *Multivariate Statistical Methods* McGraw–Hill

5 Arguments

1: MATRIX – CHARACTER(1) *Input*

On entry: selects the type of matrix on which factor analysis is to be performed.

MATRIX = 'D'

The data matrix will be input in X and factor analysis will be computed for the correlation matrix.

MATRIX = 'S'

The data matrix will be input in X and factor analysis will be computed for the covariance matrix, i.e., the results are scaled as described in Section 9.

MATRIX = 'C'

The correlation/variance-covariance matrix will be input in X and factor analysis computed for this matrix.

See Section 9.

Constraint: MATRIX = 'D', 'S' or 'C'.

- 2: WEIGHT – CHARACTER(1) *Input*
On entry: if MATRIX = 'D' or 'S', WEIGHT indicates if weights are to be used.
 WEIGHT = 'U'
 No weights are used.
 WEIGHT = 'W'
 Weights are used and must be supplied in WT.
Note: if MATRIX = 'C', WEIGHT is not referenced.
Constraint: if MATRIX = 'D' or 'S', WEIGHT = 'U' or 'W'.
- 3: N – INTEGER *Input*
On entry: if MATRIX = 'D' or 'S' the number of observations in the data array X.
 If MATRIX = 'C' the (effective) number of observations used in computing the (possibly weighted) correlation/variance-covariance matrix input in X.
Constraint: N > NVAR.
- 4: M – INTEGER *Input*
On entry: the number of variables in the data/correlation/variance-covariance matrix.
Constraint: M ≥ NVAR.
- 5: X(LDX, M) – REAL (KIND=nag_wp) array *Input*
On entry: the input matrix.
 If MATRIX = 'D' or 'S', X must contain the data matrix, i.e., X(*i*, *j*) must contain the *i*th observation for the *j*th variable, for *i* = 1, 2, ..., *n* and *j* = 1, 2, ..., M.
 If MATRIX = 'C', X must contain the correlation or variance-covariance matrix. Only the upper triangular part is required.
- 6: LDX – INTEGER *Input*
On entry: the first dimension of the array X as declared in the (sub)program from which G03CAF is called.
Constraints:
 if MATRIX = 'D' or 'S', LDX ≥ N;
 if MATRIX = 'C', LDX ≥ M.
- 7: NVAR – INTEGER *Input*
On entry: *p*, the number of variables in the factor analysis.
Constraint: NVAR ≥ 2.
- 8: ISX(M) – INTEGER array *Input*
On entry: ISX(*j*) indicates whether or not the *j*th variable is included in the factor analysis. If ISX(*j*) ≥ 1, the variable represented by the *j*th column of X is included in the analysis; otherwise it is excluded, for *j* = 1, 2, ..., M.
Constraint: ISX(*j*) > 0 for NVAR values of *j*.

- 9: NFAC – INTEGER *Input*
On entry: k , the number of factors.
Constraint: $1 \leq \text{NFAC} \leq \text{NVAR}$.
- 10: WT(*) – REAL (KIND=nag_wp) array *Input*
Note: the dimension of the array WT must be at least N if WEIGHT = 'W' and MATRIX = 'D' or 'S', and at least 1 otherwise.
On entry: if WEIGHT = 'W' and MATRIX = 'D' or 'S', WT must contain the weights to be used in the factor analysis. The effective number of observations in the analysis will then be the sum of weights. If $\text{WT}(i) = 0.0$, the i th observation is not included in the analysis.
 If WEIGHT = 'U' or MATRIX = 'C', WT is not referenced and the effective number of observations is n .
Constraint: if WEIGHT = 'W', the sum of weights $> \text{NVAR}$, $\text{WT}(i) \geq 0.0$, for $i = 1, 2, \dots, n$.
- 11: E(NVAR) – REAL (KIND=nag_wp) array *Output*
On exit: the eigenvalues θ_i , for $i = 1, 2, \dots, p$.
- 12: STAT(4) – REAL (KIND=nag_wp) array *Output*
On exit: the test statistics.
 STAT(1)
 Contains the value $F(\hat{\Psi})$.
 STAT(2)
 Contains the test statistic, χ^2 .
 STAT(3)
 Contains the degrees of freedom associated with the test statistic.
 STAT(4)
 Contains the significance level.
- 13: COM(NVAR) – REAL (KIND=nag_wp) array *Output*
On exit: the communalities.
- 14: PSI(NVAR) – REAL (KIND=nag_wp) array *Output*
On exit: the estimates of ψ_i , for $i = 1, 2, \dots, p$.
- 15: RES(NVAR \times (NVAR – 1)/2) – REAL (KIND=nag_wp) array *Output*
On exit: the residual correlations. The residual correlation for the i th and j th variables is stored in $\text{RES}((j-1)(j-2)/2 + i)$, $i < j$.
- 16: FL(LDFL, NFAC) – REAL (KIND=nag_wp) array *Output*
On exit: the factor loadings. $\text{FL}(i, j)$ contains λ_{ij} , for $i = 1, 2, \dots, p$ and $j = 1, 2, \dots, k$.
- 17: LDFL – INTEGER *Input*
On entry: the first dimension of the array FL as declared in the (sub)program from which G03CAF is called.
Constraint: $\text{LDFL} \geq \text{NVAR}$.
- 18: IOP(5) – INTEGER array *Input*
On entry: options for the optimization. There are four options to be set:

- iprint* controls iteration monitoring;
 if $iprint \leq 0$, then there is no printing of information else if $iprint > 0$, then information is printed at every $iprint$ iterations. The information printed consists of the value of $F(\Psi)$ at that iteration, the number of evaluations of $F(\Psi)$, the current estimates of the communalities and an indication of whether or not they are at the boundary.
- maxfun* the maximum number of function evaluations.
- acc* the required accuracy for the estimates of ψ_i .
- eps* a lower bound for the values of ψ , see Section 3.

Let $\epsilon = \mathbf{machine\ precision}$ then if $IOP(1) = 0$, then the following default values are used:

$$\begin{aligned} iprint &= -1 \\ maxfun &= 100p \\ acc &= 10\sqrt{\epsilon} \\ eps &= \epsilon \end{aligned}$$

If $IOP(1) \neq 0$, then

$$\begin{aligned} iprint &= IOP(2) \\ maxfun &= IOP(3) \\ acc &= 10^{-l} \text{ where } l = IOP(4) \\ eps &= 10^{-l} \text{ where } l = IOP(5) \end{aligned}$$

Constraint: if $IOP(1) \neq 0$, $IOP(i)$ must be such that $maxfun \geq 1$, $\epsilon \leq acc < 1$ and $\epsilon \leq eps < 1$, for $i = 3, 4, 5$.

- 19: IWK($4 \times NVAR + 2$) – INTEGER array *Workspace*
 20: WK(LWK) – REAL (KIND=nag_wp) array *Workspace*
 21: LWK – INTEGER *Input*

On entry: the dimension of the array WK as declared in the (sub)program from which G03CAF is called. The length of the workspace.

Constraints:

$$\begin{aligned} \text{if MATRIX = 'D' or 'S', LWK} &\geq \max((5 \times NVAR \times NVAR + 33 \times NVAR - 4)/2, \\ &N \times NVAR + 7 \times NVAR + NVAR \times (NVAR - 1)/2); \\ \text{if MATRIX = 'C', LWK} &\geq (5 \times NVAR \times NVAR + 33 \times NVAR - 4)/2. \end{aligned}$$

- 22: IFAIL – INTEGER *Input/Output*

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this argument you should refer to Section 3.4 in How to Use the NAG Library and its Documentation for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output arguments may be useful even if $IFAIL \neq 0$ on exit, the recommended value is -1. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

On exit: $IFAIL = 0$ unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry $IFAIL = 0$ or -1 , explanatory error messages are output on the current error message unit (as defined by $X04AAF$).

Note: G03CAF may return useful information for one or more of the following detected errors or warnings.

Errors or warnings detected by the routine:

$IFAIL = 1$

On entry, $LDFL < NVAR$,
 or $NVAR < 2$,
 or $N \leq NVAR$,
 or $NFAC < 1$,
 or $NVAR < NFAC$,
 or $M < NVAR$,
 or $MATRIX = 'D'$ or $'S'$ and $LDX < N$,
 or $MATRIX = 'C'$ and $LDX < M$,
 or $MATRIX \neq 'D', 'S'$ or $'C'$,
 or $MATRIX = 'D'$ or $'S'$ and $WEIGHT \neq 'U'$ or $'W'$,
 or $IOP(1) \neq 0$ and $IOP(3)$ is such that $maxfun < 1$,
 or $IOP(1) \neq 0$ and $IOP(4)$ is such that $acc \geq 1.0$,
 or $IOP(1) \neq 0$ and $IOP(4)$ is such that $acc < \mathbf{machine\ precision}$,
 or $IOP(1) \neq 0$ and $IOP(5)$ is such that $eps \geq 1.0$,
 or $IOP(1) \neq 0$ and $IOP(5)$ is such that $eps < \mathbf{machine\ precision}$,
 or $MATRIX = 'C'$ and $LWK < (5 \times NVAR \times NVAR + 33 \times NVAR - 4)/2$,
 or $MATRIX = 'D'$ or $'S'$ and
 $LWK < \max((5 \times NVAR \times NVAR + 33 \times NVAR - 4)/2, N \times NVAR + 7 \times NVAR + NVAR \times (NVAR - 1)/2)$.

$IFAIL = 2$

On entry, $WEIGHT = 'W'$ and a value of $WT < 0.0$.

$IFAIL = 3$

On entry, there are not exactly $NVAR$ elements of $ISX > 0$, or the effective number of observations $\leq NVAR$.

$IFAIL = 4$

On entry, $MATRIX = 'D'$ or $'S'$ and the data matrix is not of full column rank, or $MATRIX = 'C'$ and the input correlation/variance-covariance matrix is not positive definite.

This exit may also be caused by two of the eigenvalues of S^* being equal; this is rare (see Lawley and Maxwell (1971)), and may be due to the data/correlation matrix being almost singular.

$IFAIL = 5$

A singular value decomposition has failed to converge. This is a very unlikely error exit.

$IFAIL = 6$

The estimation procedure has failed to converge in the given number of iterations. Change IOP to either increase number of iterations $maxfun$ or increase the value of acc .

$IFAIL = 7$

The convergence is not certain but a lower point could not be found. See E04LBF for further details. In this case all results are computed.

IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.

See Section 3.9 in How to Use the NAG Library and its Documentation for further information.

IFAIL = -399

Your licence key may have expired or may not have been installed correctly.

See Section 3.8 in How to Use the NAG Library and its Documentation for further information.

IFAIL = -999

Dynamic memory allocation failed.

See Section 3.7 in How to Use the NAG Library and its Documentation for further information.

7 Accuracy

The accuracy achieved is discussed in E04LBF with the value of the argument XTOL given by *acc* as described in parameter IOP.

8 Parallelism and Performance

G03CAF is threaded by NAG for parallel execution in multithreaded implementations of the NAG Library.

G03CAF makes calls to BLAS and/or LAPACK routines, which may be threaded within the vendor library used by this implementation. Consult the documentation for the vendor library for further information.

Please consult the X06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this routine. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

9 Further Comments

The factor loadings may be orthogonally rotated by using G03BAF and factor score coefficients can be computed using G03CCF. The maximum likelihood estimators are invariant to a change in scale. This means that the results obtained will be the same (up to a scaling factor) if either the correlation matrix or the variance-covariance matrix is used. As the correlation matrix ensures that all values of ψ_i are between 0 and 1 it will lead to a more efficient optimization. In the situation when the data matrix is input the results are always computed for the correlation matrix and then scaled if the results for the covariance matrix are required. When you input the covariance/correlation matrix the input matrix itself is used and you are advised to input the correlation matrix rather than the covariance matrix.

10 Example

This example is taken from Lawley and Maxwell (1971). The correlation matrix for nine variables is input and the arguments of a factor analysis model with three factors are estimated and printed.

10.1 Program Text

```

Program g03cafe

!      G03CAF Example Program Text

!      Mark 26 Release. NAG Copyright 2016.

!      .. Use Statements ..
!      Use nag_library, Only: g03caf, nag_wp
!      .. Implicit None Statement ..

```

```

      Implicit None
!     .. Parameters ..
      Integer, Parameter          :: nin = 5, nout = 6
!     .. Local Scalars ..
      Integer                    :: i, ifail, l, ldfl, ldx, liwk, lres, &
                                lwk, lwt, m, n, nfac, nvar
      Character (1)              :: matrix, weight
!     .. Local Arrays ..
      Real (Kind=nag_wp), Allocatable :: com(:), e(:), fl(:,,:), psi(:), &
                                res(:), wk(:), wt(:), x(:,:)
      Real (Kind=nag_wp)         :: stat(4)
      Integer                    :: iop(5)
      Integer, Allocatable       :: isx(:), iwk(:)
!     .. Intrinsic Procedures ..
      Intrinsic                  :: max
!     .. Executable Statements ..
      Write (nout,*) 'G03CAF Example Program Results'
      Write (nout,*)

!     Skip headings in data file
      Read (nin,*)

!     Read in the problem size
      Read (nin,*) matrix, weight, n, m, nvar, nfac

      lwk = (5*nvar*nvar+33*nvar-4)/2
      If (matrix=='C' .Or. matrix=='c') Then
         lwt = 0
         ldx = m
      Else
         If (weight=='W' .Or. weight=='w') Then
            lwt = n
         Else
            lwt = 0
         End If
         ldx = n
         lwk = max(lwk,n*nvar+7*nvar+nvar*(nvar-1)/2)
      End If
      ldfl = nvar
      lres = nvar*(nvar-1)/2
      liwk = 4*nvar + 2
      Allocate (x(ldx,m),isx(m),wt(lwt),e(nvar),com(nvar),psi(nvar),res(lres), &
               fl(ldfl,nfac),iwk(liwk),wk(lwk))

!     Read in the data
      If (lwt>0) Then
         Read (nin,*)(x(i,1:m),wt(i),i=1,ldx)
      Else
         Read (nin,*)(x(i,1:m),i=1,ldx)
      End If

!     Read in variable inclusion flags
      Read (nin,*) isx(1:m)

!     Read in options
      Read (nin,*) iop(1:5)

!     Fit factor analysis model
      ifail = -1
      Call g03caf(matrix,weight,n,m,x,ldx,nvar,isx,nfac,wt,e,stat,com,psi,res, &
                fl,ldfl,iop,iwk,wk,lwk,ifail)
      If (ifail/=0) Then
         If (ifail<=4) Then
            Go To 100
         End If
      End If

!     Display results
      Write (nout,*) ' Eigenvalues'
      Write (nout,*)
      Write (nout,99998) e(1:nvar)

```



```

Write (nout,*)
Write (nout,99997) '      Test Statistic = ', stat(2)
Write (nout,99997) '      df = ', stat(3)
Write (nout,99997) ' Significance level = ', stat(4)
Write (nout,*)
Write (nout,*) ' Residuals'
Write (nout,*)
l = 1
Do i = 1, nvar - 1
  Write (nout,99999) res(l:(l+i-1))
  l = l + i
End Do
Write (nout,*)
Write (nout,*) ' Loadings, Communalities and PSI'
Write (nout,*)
Do i = 1, nvar
  Write (nout,99999) fl(i,1:nfac), com(i), psi(i)
End Do

100  Continue

99999 Format (2X,9F8.3)
99998 Format (2X,6E12.4)
99997 Format (A,F6.3)
      End Program g03cafe

```

10.2 Program Data

G03CAF Example Program Data

```

'C' 'U' 211 9 9 3
1.000 0.523 0.395 0.471 0.346 0.426 0.576 0.434 0.639
0.523 1.000 0.479 0.506 0.418 0.462 0.547 0.283 0.645
0.395 0.479 1.000 0.355 0.270 0.254 0.452 0.219 0.504
0.471 0.506 0.355 1.000 0.691 0.791 0.443 0.285 0.505
0.346 0.418 0.270 0.691 1.000 0.679 0.383 0.149 0.409
0.426 0.462 0.254 0.791 0.679 1.000 0.372 0.314 0.472
0.576 0.547 0.452 0.443 0.383 0.372 1.000 0.385 0.680
0.434 0.283 0.219 0.285 0.149 0.314 0.385 1.000 0.470
0.639 0.645 0.504 0.505 0.409 0.472 0.680 0.470 1.000
  1 1 1 1 1 1 1 1 1
1 -1 500 2 5

```

10.3 Program Results

G03CAF Example Program Results

Eigenvalues

```

0.1597E+02  0.4358E+01  0.1847E+01  0.1156E+01  0.1119E+01  0.1027E+01
0.9257E+00  0.8951E+00  0.8771E+00

```

```

Test Statistic = 7.149
df = 12.000
Significance level = 0.848

```

Residuals

```

0.000
-0.013  0.022
0.011 -0.005  0.023
-0.010 -0.019 -0.016  0.003
-0.005  0.011 -0.012 -0.001 -0.001
0.015 -0.022 -0.011  0.002  0.029 -0.012
-0.001 -0.011  0.013  0.005 -0.006 -0.001  0.003
-0.006  0.010 -0.005 -0.011  0.002  0.007  0.003 -0.001

```

Loadings, Communalities and PSI

```

0.664 -0.321  0.074  0.550  0.450
0.689 -0.247 -0.193  0.573  0.427

```

0.493	-0.302	-0.222	0.383	0.617
0.837	0.292	-0.035	0.788	0.212
0.705	0.315	-0.153	0.619	0.381
0.819	0.377	0.105	0.823	0.177
0.661	-0.396	-0.078	0.600	0.400
0.458	-0.296	0.491	0.538	0.462
0.766	-0.427	-0.012	0.769	0.231
