

NAG Library Routine Document

D03PJF/D03PJA

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

D03PJF/D03PJA integrates a system of linear or nonlinear parabolic partial differential equations (PDEs), in one space variable with scope for coupled ordinary differential equations (ODEs). The spatial discretization is performed using a Chebyshev C^0 collocation method, and the method of lines is employed to reduce the PDEs to a system of ODEs. The resulting system is solved using a backward differentiation formula (BDF) method or a Theta method (switching between Newton's method and functional iteration).

D03PJA is a version of D03PJF that has additional parameters in order to make it safe for use in multithreaded applications (see Section 5).

2 Specification

2.1 Specification for D03PJF

```

SUBROUTINE D03PJF (NPDE, M, TS, TOUT, PDEDEF, BNDARY, U, NBKPTS, XBKPTS, &
                  NPOLY, NPTS, X, NCODE, ODEDEF, NXI, XI, NEQN, UVINIT, &
                  RTOL, ATOL, ITOL, NORM, LAOPT, ALGOPT, RSAVE, LRSAVE, &
                  ISAVE, LISAVE, ITASK, ITRACE, IND, IFAIL)
INTEGER          NPDE, M, NBKPTS, NPOLY, NPTS, NCODE, NXI, NEQN, ITOL, &
                  LRSAVE, ISAVE(LISAVE), LISAVE, ITASK, ITRACE, IND, &
                  IFAIL
REAL (KIND=nag_wp) TS, TOUT, U(NEQN), XBKPTS(NBKPTS), X(NPTS), XI(*), &
                  RTOL(*), ATOL(*), ALGOPT(30), RSAVE(LRSAVE)
CHARACTER(1)    NORM, LAOPT
EXTERNAL        PDEDEF, BNDARY, ODEDEF, UVINIT

```

2.2 Specification for D03PJA

```

SUBROUTINE D03PJA (NPDE, M, TS, TOUT, PDEDEF, BNDARY, U, NBKPTS, XBKPTS, &
                  NPOLY, NPTS, X, NCODE, ODEDEF, NXI, XI, NEQN, UVINIT, &
                  RTOL, ATOL, ITOL, NORM, LAOPT, ALGOPT, RSAVE, LRSAVE, &
                  ISAVE, LISAVE, ITASK, ITRACE, IND, IUSER, RUSER, CWSAV, &
                  LWSAV, IWSAV, RWSAV, IFAIL)
INTEGER          NPDE, M, NBKPTS, NPOLY, NPTS, NCODE, NXI, NEQN, ITOL, &
                  LRSAVE, ISAVE(LISAVE), LISAVE, ITASK, ITRACE, IND, &
                  IUSER(*), IWSAV(505), IFAIL
REAL (KIND=nag_wp) TS, TOUT, U(NEQN), XBKPTS(NBKPTS), X(NPTS), XI(*), &
                  RTOL(*), ATOL(*), ALGOPT(30), RSAVE(LRSAVE), RUSER(*), &
                  RWSAV(1100)
LOGICAL         LWSAV(100)
CHARACTER(1)    NORM, LAOPT
CHARACTER(80)   CWSAV(10)
EXTERNAL        PDEDEF, BNDARY, ODEDEF, UVINIT

```

3 Description

D03PJF/D03PJA integrates the system of parabolic-elliptic equations and coupled ODEs

$$\sum_{j=1}^{\text{NPDE}} P_{i,j} \frac{\partial U_j}{\partial t} + Q_i = x^{-m} \frac{\partial}{\partial x} (x^m R_i), \quad i = 1, 2, \dots, \text{NPDE}, \quad a \leq x \leq b, t \geq t_0, \quad (1)$$

$$F_i(t, V, \dot{V}, \xi, U^*, U_x^*, R^*, U_t^*, U_{xt}^*) = 0, \quad i = 1, 2, \dots, \text{NCODE}, \quad (2)$$

where (1) defines the PDE part and (2) generalizes the coupled ODE part of the problem.

In (1), $P_{i,j}$ and R_i depend on x, t, U, U_x , and V ; Q_i depends on x, t, U, U_x, V and **linearly** on \dot{V} . The vector U is the set of PDE solution values

$$U(x, t) = [U_1(x, t), \dots, U_{\text{NPDE}}(x, t)]^T,$$

and the vector U_x is the partial derivative with respect to x . Note that $P_{i,j}$, Q_i and R_i must not depend on $\frac{\partial U}{\partial t}$. The vector V is the set of ODE solution values

$$V(t) = [V_1(t), \dots, V_{\text{NCODE}}(t)]^T,$$

and \dot{V} denotes its derivative with respect to time.

In (2), ξ represents a vector of n_ξ spatial coupling points at which the ODEs are coupled to the PDEs. These points may or may not be equal to some of the PDE spatial mesh points. U^* , U_x^* , R^* , U_t^* and U_{xt}^* are the functions U , U_x , R , U_t and U_{xt} evaluated at these coupling points. Each F_i may only depend linearly on time derivatives. Hence the equation (2) may be written more precisely as

$$F = G - A\dot{V} - B \begin{pmatrix} U_t^* \\ U_{xt}^* \end{pmatrix}, \quad (3)$$

where $F = [F_1, \dots, F_{\text{NCODE}}]^T$, G is a vector of length NCODE, A is an NCODE by NCODE matrix, B is an NCODE by $(n_\xi \times \text{NPDE})$ matrix and the entries in G , A and B may depend on t, ξ, U^*, U_x^* and V . In practice you need only supply a vector of information to define the ODEs and not the matrices A and B . (See Section 5 for the specification of ODEDEF.)

The integration in time is from t_0 to t_{out} , over the space interval $a \leq x \leq b$, where $a = x_1$ and $b = x_{\text{NBKPTS}}$ are the leftmost and rightmost of a user-defined set of break points $x_1, x_2, \dots, x_{\text{NBKPTS}}$. The coordinate system in space is defined by the value of m ; $m = 0$ for Cartesian coordinates, $m = 1$ for cylindrical polar coordinates and $m = 2$ for spherical polar coordinates.

The PDE system which is defined by the functions $P_{i,j}$, Q_i and R_i must be specified in PDEDEF.

The initial values of the functions $U(x, t)$ and $V(t)$ must be given at $t = t_0$. These values are calculated in UVINIT.

The functions R_i which may be thought of as fluxes, are also used in the definition of the boundary conditions. The boundary conditions must have the form

$$\beta_i(x, t)R_i(x, t, U, U_x, V) = \gamma_i(x, t, U, U_x, V, \dot{V}), \quad i = 1, 2, \dots, \text{NPDE}, \quad (4)$$

where $x = a$ or $x = b$. The functions γ_i may only depend **linearly** on \dot{V} .

The boundary conditions must be specified in BNDARY.

The algebraic-differential equation system which is defined by the functions F_i must be specified in ODEDEF. You must also specify the coupling points ξ in the array XI. Thus, the problem is subject to the following restrictions:

- (i) in (1), $\dot{V}_j(t)$, for $j = 1, 2, \dots, \text{NCODE}$, may only appear **linearly** in the functions Q_i , for $i = 1, 2, \dots, \text{NPDE}$, with a similar restriction for γ ;
- (ii) $P_{i,j}$ and the flux R_i must not depend on any time derivatives;
- (iii) $t_0 < t_{\text{out}}$, so that integration is in the forward direction;
- (iv) the evaluation of the functions $P_{i,j}$, Q_i and R_i is done at both the break points and internally selected points for each element in turn, that is $P_{i,j}$, Q_i and R_i are evaluated twice at each break point. Any discontinuities in these functions **must** therefore be at one or more of the mesh points;

- (v) at least one of the functions $P_{i,j}$ must be nonzero so that there is a time derivative present in the PDE problem;
- (vi) if $m > 0$ and $x_1 = 0.0$, which is the left boundary point, then it must be ensured that the PDE solution is bounded at this point. This can be done either by specifying the solution at $x = 0.0$ or by specifying a zero flux there, that is $\beta_i = 1.0$ and $\gamma_i = 0.0$.

The parabolic equations are approximated by a system of ODEs in time for the values of U_i at the mesh points. This ODE system is obtained by approximating the PDE solution between each pair of break points by a Chebyshev polynomial of degree NPOLY. The interval between each pair of break points is treated by D03PJF/D03PJA as an element, and on this element, a polynomial and its space and time derivatives are made to satisfy the system of PDEs at NPOLY – 1 spatial points, which are chosen internally by the code and the break points. The user-defined break points and the internally selected points together define the mesh. The smallest value that NPOLY can take is one, in which case, the solution is approximated by piecewise linear polynomials between consecutive break points and the method is similar to an ordinary finite element method.

In total there are $(\text{NBKPTS} - 1) \times \text{NPOLY} + 1$ mesh points in the spatial direction, and $\text{NPDE} \times ((\text{NBKPTS} - 1) \times \text{NPOLY} + 1) + \text{NCODE}$ ODEs in the time direction; one ODE at each break point for each PDE component, NPOLY – 1 ODEs for each PDE component between each pair of break points, and NCODE coupled ODEs. The system is then integrated forwards in time using a Backward Differentiation Formula (BDF) method or a Theta method.

4 References

Berzins M (1990) Developments in the NAG Library software for parabolic equations *Scientific Software Systems* (eds J C Mason and M G Cox) 59–72 Chapman and Hall

Berzins M and Dew P M (1991) Algorithm 690: Chebyshev polynomial software for elliptic-parabolic systems of PDEs *ACM Trans. Math. Software* **17** 178–206

Berzins M, Dew P M and Furzeland R M (1988) Software tools for time-dependent equations in simulation and optimization of large systems *Proc. IMA Conf. Simulation and Optimization* (ed A J Osiadcz) 35–50 Clarendon Press, Oxford

Berzins M and Furzeland R M (1992) An adaptive theta method for the solution of stiff and nonstiff differential equations *Appl. Numer. Math.* **9** 1–19

Zaturka N B, Drazin P G and Banks W H H (1988) On the flow of a viscous fluid driven along a channel by a suction at porous walls *Fluid Dynamics Research* **4**

5 Parameters

1: NPDE – INTEGER *Input*

On entry: the number of PDEs to be solved.

Constraint: NPDE \geq 1.

2: M – INTEGER *Input*

On entry: the coordinate system used:

M = 0

Indicates Cartesian coordinates.

M = 1

Indicates cylindrical polar coordinates.

M = 2

Indicates spherical polar coordinates.

Constraint: M = 0, 1 or 2.

- 3: TS – REAL (KIND=nag_wp) Input/Output
On entry: the initial value of the independent variable t .
On exit: the value of t corresponding to the solution values in U. Normally TS = TOUT.
Constraint: TS < TOUT.
- 4: TOUT – REAL (KIND=nag_wp) Input
On entry: the final value of t to which the integration is to be carried out.
- 5: PDEDEF – SUBROUTINE, supplied by the user. External Procedure
 PDEDEF must compute the functions $P_{i,j}$, Q_i and R_i which define the system of PDEs. The functions may depend on x , t , U , U_x and V ; Q_i may depend linearly on \dot{V} . The functions must be evaluated at a set of points.

The specification of PDEDEF for D03PJF is:

```

SUBROUTINE PDEDEF (NPDE, T, X, NPTL, U, UX, NCODE, V, VDOT, P, Q, R,      &
                  IRES)
INTEGER          NPDE, NPTL, NCODE, IRES
REAL (KIND=nag_wp) T, X(NPTL), U(NPDE,NPTL), UX(NPDE,NPTL),      &
                  V(NCODE), VDOT(NCODE), P(NPDE,NPDE,NPTL),      &
                  Q(NPDE,NPTL), R(NPDE,NPTL)

```

The specification of PDEDEF for D03PJA is:

```

SUBROUTINE PDEDEF (NPDE, T, X, NPTL, U, UX, NCODE, V, VDOT, P, Q, R,      &
                  IRES, IUSER, RUSER)
INTEGER          NPDE, NPTL, NCODE, IRES, IUSER(*)
REAL (KIND=nag_wp) T, X(NPTL), U(NPDE,NPTL), UX(NPDE,NPTL),      &
                  V(NCODE), VDOT(NCODE), P(NPDE,NPDE,NPTL),      &
                  Q(NPDE,NPTL), R(NPDE,NPTL), RUSER(*)

```

- 1: NPDE – INTEGER Input
On entry: the number of PDEs in the system.
- 2: T – REAL (KIND=nag_wp) Input
On entry: the current value of the independent variable t .
- 3: X(NPTL) – REAL (KIND=nag_wp) array Input
On entry: contains a set of mesh points at which $P_{i,j}$, Q_i and R_i are to be evaluated. X(1) and X(NPTL) contain successive user-supplied break points and the elements of the array will satisfy $X(1) < X(2) < \dots < X(NPTL)$.
- 4: NPTL – INTEGER Input
On entry: the number of points at which evaluations are required (the value of NPOLY + 1).
- 5: U(NPDE,NPTL) – REAL (KIND=nag_wp) array Input
On entry: U(i,j) contains the value of the component $U_i(x,t)$ where $x = X(j)$, for $i = 1, 2, \dots, NPDE$ and $j = 1, 2, \dots, NPTL$.
- 6: UX(NPDE,NPTL) – REAL (KIND=nag_wp) array Input
On entry: UX(i,j) contains the value of the component $\frac{\partial U_i(x,t)}{\partial x}$ where $x = X(j)$, for $i = 1, 2, \dots, NPDE$ and $j = 1, 2, \dots, NPTL$.

7:	NCODE – INTEGER	<i>Input</i>
	<i>On entry:</i> the number of coupled ODEs in the system.	
8:	V(NCODE) – REAL (KIND=nag_wp) array	<i>Input</i>
	<i>On entry:</i> if NCODE > 0, V(<i>i</i>) contains the value of the component $V_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$.	
9:	VDOT(NCODE) – REAL (KIND=nag_wp) array	<i>Input</i>
	<i>On entry:</i> if NCODE > 0, VDOT(<i>i</i>) contains the value of component $\dot{V}_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$.	
	Note: $\dot{V}_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$, may only appear linearly in Q_j , for $j = 1, 2, \dots, \text{NPDE}$.	
10:	P(NPDE,NPDE,NPTL) – REAL (KIND=nag_wp) array	<i>Output</i>
	<i>On exit:</i> P(<i>i, j, k</i>) must be set to the value of $P_{i,j}(x, t, U, U_x, V)$ where $x = X(k)$, for $i = 1, 2, \dots, \text{NPDE}$, $j = 1, 2, \dots, \text{NPDE}$ and $k = 1, 2, \dots, \text{NPTL}$.	
11:	Q(NPDE,NPTL) – REAL (KIND=nag_wp) array	<i>Output</i>
	<i>On exit:</i> Q(<i>i, j</i>) must be set to the value of $Q_i(x, t, U, U_x, V, \dot{V})$ where $x = X(j)$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NPTL}$.	
12:	R(NPDE,NPTL) – REAL (KIND=nag_wp) array	<i>Output</i>
	<i>On exit:</i> R(<i>i, j</i>) must be set to the value of $R_i(x, t, U, U_x, V)$ where $x = X(i)$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NPTL}$.	
13:	IRES – INTEGER	<i>Input/Output</i>
	<i>On entry:</i> set to -1 or 1 .	
	<i>On exit:</i> should usually remain unchanged. However, you may set IRES to force the integration routine to take certain actions as described below:	
	IRES = 2	
	Indicates to the integrator that control should be passed back immediately to the calling (sub)routin with the error indicator set to IFAIL = 6.	
	IRES = 3	
	Indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. You may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If you consecutively set IRES = 3, then D03PJF/D03PJA returns to the calling subroutine with the error indicator set to IFAIL = 4.	
	Note: the following are additional parameters for specific use with D03PJA. Users of D03PJF therefore need not read the remainder of this description.	
14:	IUSER(*) – INTEGER array	<i>User Workspace</i>
15:	RUSER(*) – REAL (KIND=nag_wp) array	<i>User Workspace</i>
	PDEDEF is called with the parameters IUSER and RUSER as supplied to D03PJF/D03PJA. You are free to use the arrays IUSER and RUSER to supply information to PDEDEF as an alternative to using COMMON global variables.	

PDEDEF must either be a module subprogram USED by, or declared as EXTERNAL in, the (sub)program from which D03PJF/D03PJA is called. Parameters denoted as *Input* must **not** be changed by this procedure.

6: BNDARY – SUBROUTINE, supplied by the user.

External Procedure

BNDARY must compute the functions β_i and γ_i which define the boundary conditions as in equation (4).

The specification of BNDARY for D03PJF is:

```

SUBROUTINE BNDARY (NPDE, T, U, UX, NCODE, V, VDOT, IBND, BETA,      &
                  GAMMA, IRES)
INTEGER            NPDE, NCODE, IBND, IRES
REAL (KIND=nag_wp) T, U(NPDE), UX(NPDE), V(NCODE), VDOT(NCODE),  &
                  BETA(NPDE), GAMMA(NPDE)

```

The specification of BNDARY for D03PJA is:

```

SUBROUTINE BNDARY (NPDE, T, U, UX, NCODE, V, VDOT, IBND, BETA,      &
                  GAMMA, IRES, IUSER, RUSER)
INTEGER            NPDE, NCODE, IBND, IRES, IUSER(*)
REAL (KIND=nag_wp) T, U(NPDE), UX(NPDE), V(NCODE), VDOT(NCODE),  &
                  BETA(NPDE), GAMMA(NPDE), RUSER(*)

```

1: NPDE – INTEGER *Input*

On entry: the number of PDEs in the system.

2: T – REAL (KIND=nag_wp) *Input*

On entry: the current value of the independent variable t .

3: U(NPDE) – REAL (KIND=nag_wp) array *Input*

On entry: $U(i)$ contains the value of the component $U_i(x, t)$ at the boundary specified by IBND, for $i = 1, 2, \dots, NPDE$.

4: UX(NPDE) – REAL (KIND=nag_wp) array *Input*

On entry: $UX(i)$ contains the value of the component $\frac{\partial U_i(x, t)}{\partial x}$ at the boundary specified by IBND, for $i = 1, 2, \dots, NPDE$.

5: NCODE – INTEGER *Input*

On entry: the number of coupled ODEs in the system.

6: V(NCODE) – REAL (KIND=nag_wp) array *Input*

On entry: if $NCODE > 0$, $V(i)$ contains the value of the component $V_i(t)$, for $i = 1, 2, \dots, NCODE$.

7: VDOT(NCODE) – REAL (KIND=nag_wp) array *Input*

On entry: if $NCODE > 0$, $VDOT(i)$ contains the value of component $\dot{V}_i(t)$, for $i = 1, 2, \dots, NCODE$.

Note: $\dot{V}_i(t)$, for $i = 1, 2, \dots, NCODE$, may only appear linearly in Q_j , for $j = 1, 2, \dots, NPDE$.

8: IBND – INTEGER *Input*

On entry: specifies which boundary conditions are to be evaluated.

IBND = 0

BNDARY must set up the coefficients of the left-hand boundary, $x = a$.

	IBND $\neq 0$ BNDARY must set up the coefficients of the right-hand boundary, $x = b$.	
9:	BETA(NPDE) – REAL (KIND=nag_wp) array <i>On exit:</i> BETA(i) must be set to the value of $\beta_i(x, t)$ at the boundary specified by IBND, for $i = 1, 2, \dots, \text{NPDE}$.	Output
10:	GAMMA(NPDE) – REAL (KIND=nag_wp) array <i>On exit:</i> GAMMA(i) must be set to the value of $\gamma_i(x, t, U, U_x, V, \dot{V})$ at the boundary specified by IBND, for $i = 1, 2, \dots, \text{NPDE}$.	Output
11:	IRES – INTEGER <i>On entry:</i> set to -1 or 1 . <i>On exit:</i> should usually remain unchanged. However, you may set IRES to force the integration routine to take certain actions as described below: IRES = 2 Indicates to the integrator that control should be passed back immediately to the calling (sub)routinewith the error indicator set to IFAIL = 6. IRES = 3 Indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. You may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If you consecutively set IRES = 3, then D03PJF/D03PJA returns to the calling subroutine with the error indicator set to IFAIL = 4.	Input/Output
	Note: <i>the following are additional parameters for specific use with D03PJA. Users of D03PJF therefore need not read the remainder of this description.</i>	
12:	IUSER(*) – INTEGER array	User Workspace
13:	RUSER(*) – REAL (KIND=nag_wp) array	User Workspace
	BNDARY is called with the parameters IUSER and RUSER as supplied to D03PJF/D03PJA. You are free to use the arrays IUSER and RUSER to supply information to BNDARY as an alternative to using COMMON global variables.	

BNDARY must either be a module subprogram USED by, or declared as EXTERNAL in, the (sub)program from which D03PJF/D03PJA is called. Parameters denoted as *Input* must **not** be changed by this procedure.

- 7: U(NEQN) – REAL (KIND=nag_wp) array Input/Output
On entry: if IND = 1 the value of U must be unchanged from the previous call.
On exit: the computed solution $U_i(x_j, t)$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NPTS}$, and $V_k(t)$, for $k = 1, 2, \dots, \text{NCODE}$, evaluated at $t = \text{TS}$, as follows:
U(NPDE \times (j - 1) + i) contain $U_i(x_j, t)$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NPTS}$,
and
U(NPTS \times NPDE + i) contain $V_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$.
- 8: NBKPTS – INTEGER Input
On entry: the number of break points in the interval $[a, b]$.
Constraint: NBKPTS ≥ 2 .

- 9: XBKPTS(NBKPTS) – REAL (KIND=nag_wp) array Input
On entry: the values of the break points in the space direction. XBKPTS(1) must specify the left-hand boundary, a , and XBKPTS(NBKPTS) must specify the right-hand boundary, b .
Constraint: $\text{XBKPTS}(1) < \text{XBKPTS}(2) < \dots < \text{XBKPTS}(\text{NBKPTS})$.
- 10: NPOLY – INTEGER Input
On entry: the degree of the Chebyshev polynomial to be used in approximating the PDE solution between each pair of break points.
Constraint: $1 \leq \text{NPOLY} \leq 49$.
- 11: NPTS – INTEGER Input
On entry: the number of mesh points in the interval $[a, b]$.
Constraint: $\text{NPTS} = (\text{NBKPTS} - 1) \times \text{NPOLY} + 1$.
- 12: X(NPTS) – REAL (KIND=nag_wp) array Output
On exit: the mesh points chosen by D03PJF/D03PJA in the spatial direction. The values of X will satisfy $X(1) < X(2) < \dots < X(\text{NPTS})$.
- 13: NCODE – INTEGER Input
On entry: the number of coupled ODE components.
Constraint: $\text{NCODE} \geq 0$.
- 14: ODEDEF – SUBROUTINE, supplied by the NAG Library or the user. External Procedure
 ODEDEF must evaluate the functions F , which define the system of ODEs, as given in (3).
 If you wish to compute the solution of a system of PDEs only ($\text{NCODE} = 0$), ODEDEF must be the dummy routine D03PCK/D53PCK for D03PJF (or D53PCK for D03PJA). D03PCK/D53PCK and D53PCK are included in the NAG Library.

The specification of ODEDEF for D03PJF is:

```

SUBROUTINE ODEDEF (NPDE, T, NCODE, V, VDOT, NXI, XI, UCP, UCPX, RCP,      &
                  UCPT, UCPTX, F, IRES)
INTEGER          NPDE, NCODE, NXI, IRES
REAL (KIND=nag_wp) T, V(NCODE), VDOT(NCODE), XI(NXI), UCP(NPDE,*),    &
                  UCPX(NPDE,*), RCP(NPDE,*), UCPT(NPDE,*),          &
                  UCPTX(NPDE,*), F(NCODE)

```

The specification of ODEDEF for D03PJA is:

```

SUBROUTINE ODEDEF (NPDE, T, NCODE, V, VDOT, NXI, XI, UCP, UCPX, RCP,      &
                  UCPT, UCPTX, F, IRES, IUSER, RUSER)
INTEGER          NPDE, NCODE, NXI, IRES, IUSER(*)
REAL (KIND=nag_wp) T, V(NCODE), VDOT(NCODE), XI(NXI), UCP(NPDE,*),    &
                  UCPX(NPDE,*), RCP(NPDE,*), UCPT(NPDE,*),          &
                  UCPTX(NPDE,*), F(NCODE), RUSER(*)

```

- 1: NPDE – INTEGER Input
On entry: the number of PDEs in the system.
- 2: T – REAL (KIND=nag_wp) Input
On entry: the current value of the independent variable t .

- | | | |
|-----|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| 3: | NCODE – INTEGER
<i>On entry:</i> the number of coupled ODEs in the system. | <i>Input</i> |
| 4: | V(NCODE) – REAL (KIND=nag_wp) array
<i>On entry:</i> if NCODE > 0, V(<i>i</i>) contains the value of the component $V_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$. | <i>Input</i> |
| 5: | VDOT(NCODE) – REAL (KIND=nag_wp) array
<i>On entry:</i> if NCODE > 0, VDOT(<i>i</i>) contains the value of component $\dot{V}_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$. | <i>Input</i> |
| 6: | NXI – INTEGER
<i>On entry:</i> the number of ODE/PDE coupling points. | <i>Input</i> |
| 7: | XI(NXI) – REAL (KIND=nag_wp) array
<i>On entry:</i> if NXI > 0, XI(<i>i</i>) contains the ODE/PDE coupling points, ξ_i , for $i = 1, 2, \dots, \text{NXI}$. | <i>Input</i> |
| 8: | UCP(NPDE,*) – REAL (KIND=nag_wp) array
<i>On entry:</i> if NXI > 0, UCP(<i>i, j</i>) contains the value of $U_i(x, t)$ at the coupling point $x = \xi_j$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NXI}$. | <i>Input</i> |
| 9: | UCPX(NPDE,*) – REAL (KIND=nag_wp) array
<i>On entry:</i> if NXI > 0, UCPX(<i>i, j</i>) contains the value of $\frac{\partial U_i(x, t)}{\partial x}$ at the coupling point $x = \xi_j$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NXI}$. | <i>Input</i> |
| 10: | RCP(NPDE,*) – REAL (KIND=nag_wp) array
<i>On entry:</i> RCP(<i>i, j</i>) contains the value of the flux R_i at the coupling point $x = \xi_j$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NXI}$. | <i>Input</i> |
| 11: | UCPT(NPDE,*) – REAL (KIND=nag_wp) array
<i>On entry:</i> if NXI > 0, UCPT(<i>i, j</i>) contains the value of $\frac{\partial U_i}{\partial t}$ at the coupling point $x = \xi_j$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NXI}$. | <i>Input</i> |
| 12: | UCPTX(NPDE,*) – REAL (KIND=nag_wp) array
<i>On entry:</i> UCPTX(<i>i, j</i>) contains the value of $\frac{\partial^2 U_i}{\partial x \partial t}$ at the coupling point $x = \xi_j$, for $i = 1, 2, \dots, \text{NPDE}$ and $j = 1, 2, \dots, \text{NXI}$. | <i>Input</i> |
| 13: | F(NCODE) – REAL (KIND=nag_wp) array
<i>On exit:</i> F(<i>i</i>) must contain the <i>i</i> th component of F , for $i = 1, 2, \dots, \text{NCODE}$, where F is defined as | <i>Output</i> |

$$F = G - A\dot{V} - B \begin{pmatrix} U_t^* \\ U_{xt}^* \end{pmatrix}, \quad (5)$$

or

$$F = -A\dot{V} - B \begin{pmatrix} U_t^* \\ U_{xt}^* \end{pmatrix}. \quad (6)$$

The definition of F is determined by the input value of IRES.

14:	<p>IRES – INTEGER</p> <p><i>On entry:</i> the form of F that must be returned in the array F.</p> <p>IRES = 1 Equation (5) must be used.</p> <p>IRES = -1 Equation (6) must be used.</p> <p><i>On exit:</i> should usually remain unchanged. However, you may reset IRES to force the integration routine to take certain actions as described below:</p> <p>IRES = 2 Indicates to the integrator that control should be passed back immediately to the calling (sub)routine with the error indicator set to IFAIL = 6.</p> <p>IRES = 3 Indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. You may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If you consecutively set IRES = 3, then D03PJF/D03PJA returns to the calling subroutine with the error indicator set to IFAIL = 4.</p> <p>Note: <i>the following are additional parameters for specific use with D03PJA. Users of D03PJF therefore need not read the remainder of this description.</i></p>	Input/Output
15:	IUSER(*) – INTEGER array	User Workspace
16:	RUSER(*) – REAL (KIND=nag_wp) array	User Workspace
	<p>ODEDEF is called with the parameters IUSER and RUSER as supplied to D03PJF/D03PJA. You are free to use the arrays IUSER and RUSER to supply information to ODEDEF as an alternative to using COMMON global variables.</p>	

ODEDEF must either be a module subprogram USED by, or declared as EXTERNAL in, the (sub)program from which D03PJF/D03PJA is called. Parameters denoted as *Input* must **not** be changed by this procedure.

- 15: NXI – INTEGER *Input*
- On entry:* the number of ODE/PDE coupling points.
- Constraints:*
- if NCODE = 0, NXI = 0;
if NCODE > 0, NXI ≥ 0.
- 16: XI(*) – REAL (KIND=nag_wp) array *Input*
- Note:** the dimension of the array XI must be at least max(1, NXI).
- On entry:* XI(i), for $i = 1, 2, \dots, NXI$, must be set to the ODE/PDE coupling points.
- Constraint:* $XBKPTS(1) \leq XI(1) < XI(2) < \dots < XI(NXI) \leq XBKPTS(NBKPTS)$.
- 17: NEQN – INTEGER *Input*
- On entry:* the number of ODEs in the time direction.
- Constraint:* $NEQN = NPDE \times NPTS + NCODE$.
- 18: UVINIT – SUBROUTINE, supplied by the user. *External Procedure*
- UVINIT must compute the initial values of the PDE and the ODE components $U_i(x_j, t_0)$, for $i = 1, 2, \dots, NPDE$ and $j = 1, 2, \dots, NPTS$, and $V_k(t_0)$, for $k = 1, 2, \dots, NCODE$.

The specification of UVINIT for D03PJF is:

```
SUBROUTINE UVINIT (NPDE, NPTS, X, U, NCODE, V)
INTEGER          NPDE, NPTS, NCODE
REAL (KIND=nag_wp) X(NPTS), U(NPDE,NPTS), V(NCODE)
```

The specification of UVINIT for D03PJA is:

```
SUBROUTINE UVINIT (NPDE, NPTS, X, U, NCODE, V, IUSER, RUSER)
INTEGER          NPDE, NPTS, NCODE, IUSER(*)
REAL (KIND=nag_wp) X(NPTS), U(NPDE,NPTS), V(NCODE), RUSER(*)
```

- | | | |
|----|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------|
| 1: | NPDE – INTEGER | <i>Input</i> |
| | <i>On entry:</i> the number of PDEs in the system. | |
| 2: | NPTS – INTEGER | <i>Input</i> |
| | <i>On entry:</i> the number of mesh points in the interval $[a, b]$. | |
| 3: | X(NPTS) – REAL (KIND=nag_wp) array | <i>Input</i> |
| | <i>On entry:</i> $X(i)$, for $i = 1, 2, \dots, NPTS$, contains the current values of the space variable x_i . | |
| 4: | U(NPDE,NPTS) – REAL (KIND=nag_wp) array | <i>Output</i> |
| | <i>On exit:</i> if $NXI > 0$, $U(i, j)$ contains the value of the component $U_i(x_j, t_0)$, for $i = 1, 2, \dots, NPDE$ and $j = 1, 2, \dots, NPTS$. | |
| 5: | NCODE – INTEGER | <i>Input</i> |
| | <i>On entry:</i> the number of coupled ODEs in the system. | |
| 6: | V(NCODE) – REAL (KIND=nag_wp) array | <i>Output</i> |
| | <i>On exit:</i> $V(i)$ contains the value of component $V_i(t_0)$, for $i = 1, 2, \dots, NCODE$. | |
| | Note: <i>the following are additional parameters for specific use with D03PJA. Users of D03PJF therefore need not read the remainder of this description.</i> | |
| 7: | IUSER(*) – INTEGER array | <i>User Workspace</i> |
| 8: | RUSER(*) – REAL (KIND=nag_wp) array | <i>User Workspace</i> |

UVINIT is called with the parameters IUSER and RUSER as supplied to D03PJF/D03PJA. You are free to use the arrays IUSER and RUSER to supply information to UVINIT as an alternative to using COMMON global variables.

UVINIT must either be a module subprogram USED by, or declared as EXTERNAL in, the (sub)program from which D03PJF/D03PJA is called. Parameters denoted as *Input* must **not** be changed by this procedure.

- | | | |
|-----|------------------------------------|--------------|
| 19: | RTOL(*) – REAL (KIND=nag_wp) array | <i>Input</i> |
|-----|------------------------------------|--------------|

Note: the dimension of the array RTOL must be at least 1 if ITOL = 1 or 2 and at least NEQN if ITOL = 3 or 4.

On entry: the relative local error tolerance.

Constraint: $RTOL(i) \geq 0.0$ for all relevant i .

20: ATOL(*) – REAL (KIND=nag_wp) array Input

Note: the dimension of the array ATOL must be at least 1 if ITOL = 1 or 3 and at least NEQN if ITOL = 2 or 4.

On entry: the absolute local error tolerance.

Constraint: $ATOL(i) \geq 0.0$ for all relevant i .

Note: corresponding elements of RTOL and ATOL cannot both be 0.0.

21: ITOL – INTEGER Input

On entry: a value to indicate the form of the local error test. ITOL indicates to D03PJF/D03PJA whether to interpret either or both of RTOL or ATOL as a vector or scalar. The error test to be satisfied is $\|e_i/w_i\| < 1.0$, where w_i is defined as follows:

ITOL	RTOL	ATOL	w_i
1	scalar	scalar	$RTOL(1) \times U_i + ATOL(1)$
2	scalar	vector	$RTOL(1) \times U_i + ATOL(i)$
3	vector	scalar	$RTOL(i) \times U_i + ATOL(1)$
4	vector	vector	$RTOL(i) \times U_i + ATOL(i)$

In the above, e_i denotes the estimated local error for the i th component of the coupled PDE/ODE system in time, $U(i)$, for $i = 1, 2, \dots, NEQN$.

The choice of norm used is defined by the parameter NORM.

Constraint: $1 \leq ITOL \leq 4$.

22: NORM – CHARACTER(1) Input

On entry: the type of norm to be used.

NORM = 'M'

Maximum norm.

NORM = 'A'

Averaged L_2 norm.

If U_{norm} denotes the norm of the vector U of length NEQN, then for the averaged L_2 norm

$$U_{\text{norm}} = \sqrt{\frac{1}{NEQN} \sum_{i=1}^{NEQN} (U(i)/w_i)^2},$$

while for the maximum norm

$$U_{\text{norm}} = \max_i |U(i)/w_i|.$$

See the description of ITOL for the formulation of the weight vector w .

Constraint: NORM = 'M' or 'A'.

23: LAOPT – CHARACTER(1) Input

On entry: the type of matrix algebra required.

LAOPT = 'F'

Full matrix methods to be used.

LAOPT = 'B'

Banded matrix methods to be used.

LAOPT = 'S'

Sparse matrix methods to be used.

Constraint: LAOPT = 'F', 'B' or 'S'.

Note: you are recommended to use the banded option when no coupled ODEs are present (i.e., NCODE = 0).

24: ALGOPT(30) – REAL (KIND=nag_wp) array *Input*

On entry: may be set to control various options available in the integrator. If you wish to employ all the default options, then ALGOPT(1) should be set to 0.0. Default values will also be used for any other elements of ALGOPT set to zero. The permissible values, default values, and meanings are as follows:

ALGOPT(1)

Selects the ODE integration method to be used. If ALGOPT(1) = 1.0, a BDF method is used and if ALGOPT(1) = 2.0, a Theta method is used. The default value is ALGOPT(1) = 1.0.

If ALGOPT(1) = 2.0, then ALGOPT(i), for $i = 2, 3, 4$ are not used.

ALGOPT(2)

Specifies the maximum order of the BDF integration formula to be used. ALGOPT(2) may be 1.0, 2.0, 3.0, 4.0 or 5.0. The default value is ALGOPT(2) = 5.0.

ALGOPT(3)

Specifies what method is to be used to solve the system of nonlinear equations arising on each step of the BDF method. If ALGOPT(3) = 1.0 a modified Newton iteration is used and if ALGOPT(3) = 2.0 a functional iteration method is used. If functional iteration is selected and the integrator encounters difficulty, then there is an automatic switch to the modified Newton iteration. The default value is ALGOPT(3) = 1.0.

ALGOPT(4)

Specifies whether or not the Petzold error test is to be employed. The Petzold error test results in extra overhead but is more suitable when algebraic equations are present, such as $P_{i,j} = 0.0$, for $j = 1, 2, \dots, \text{NPDE}$, for some i or when there is no $\dot{V}_i(t)$ dependence in the coupled ODE system. If ALGOPT(4) = 1.0, then the Petzold test is used. If ALGOPT(4) = 2.0, then the Petzold test is not used. The default value is ALGOPT(4) = 1.0.

If ALGOPT(1) = 1.0, then ALGOPT(i), for $i = 5, 6, 7$, are not used.

ALGOPT(5)

Specifies the value of Theta to be used in the Theta integration method. $0.51 \leq \text{ALGOPT}(5) \leq 0.99$. The default value is ALGOPT(5) = 0.55.

ALGOPT(6)

Specifies what method is to be used to solve the system of nonlinear equations arising on each step of the Theta method. If ALGOPT(6) = 1.0, a modified Newton iteration is used and if ALGOPT(6) = 2.0, a functional iteration method is used. The default value is ALGOPT(6) = 1.0.

ALGOPT(7)

Specifies whether or not the integrator is allowed to switch automatically between modified Newton and functional iteration methods in order to be more efficient. If ALGOPT(7) = 1.0, then switching is allowed and if ALGOPT(7) = 2.0, then switching is not allowed. The default value is ALGOPT(7) = 1.0.

ALGOPT(11)

Specifies a point in the time direction, t_{crit} , beyond which integration must not be attempted. The use of t_{crit} is described under the parameter ITASK. If ALGOPT(1) \neq 0.0, a value of 0.0 for ALGOPT(11), say, should be specified even if ITASK subsequently specifies that t_{crit} will not be used.

ALGOPT(12)

Specifies the minimum absolute step size to be allowed in the time integration. If this option is not required, ALGOPT(12) should be set to 0.0.

ALGOPT(13)

Specifies the maximum absolute step size to be allowed in the time integration. If this option is not required, ALGOPT(13) should be set to 0.0.

ALGOPT(14)

Specifies the initial step size to be attempted by the integrator. If ALGOPT(14) = 0.0, then the initial step size is calculated internally.

ALGOPT(15)

Specifies the maximum number of steps to be attempted by the integrator in any one call. If ALGOPT(15) = 0.0, then no limit is imposed.

ALGOPT(23)

Specifies what method is to be used to solve the nonlinear equations at the initial point to initialize the values of U , U_t , V and \dot{V} . If ALGOPT(23) = 1.0, a modified Newton iteration is used and if ALGOPT(23) = 2.0, functional iteration is used. The default value is ALGOPT(23) = 1.0.

ALGOPT(29) and ALGOPT(30) are used only for the sparse matrix algebra option, LAOPT = 'S'.

ALGOPT(29)

Governs the choice of pivots during the decomposition of the first Jacobian matrix. It should lie in the range $0.0 < \text{ALGOPT}(29) < 1.0$, with smaller values biasing the algorithm towards maintaining sparsity at the expense of numerical stability. If ALGOPT(29) lies outside this range then the default value is used. If the routines regard the Jacobian matrix as numerically singular then increasing ALGOPT(29) towards 1.0 may help, but at the cost of increased fill-in. The default value is ALGOPT(29) = 0.1.

ALGOPT(30)

Is used as a relative pivot threshold during subsequent Jacobian decompositions (see ALGOPT(29)) below which an internal error is invoked. If ALGOPT(30) is greater than 1.0 no check is made on the pivot size, and this may be a necessary option if the Jacobian is found to be numerically singular (see ALGOPT(29)). The default value is ALGOPT(30) = 0.0001.

25: RSAVE(LRSAVE) – REAL (KIND=nag_wp) array

Communication Array

If IND = 0, RSAVE need not be set on entry.

If IND = 1, RSAVE must be unchanged from the previous call to the routine because it contains required information about the iteration.

26: LRSAVE – INTEGER

Input

On entry: the dimension of the array RSAVE as declared in the (sub)program from which D03PJF/D03PJA is called. Its size depends on the type of matrix algebra selected.

If LAOPT = 'F', $\text{LRSAVE} \geq \text{NEQN} \times \text{NEQN} + \text{NEQN} + \text{nwkres} + \text{lenode}$.

If LAOPT = 'B', $\text{LRSAVE} \geq (3 \times \text{mlu} + 1) \times \text{NEQN} + \text{nwkres} + \text{lenode}$.

If LAOPT = 'S', $\text{LRSAVE} \geq 4 \times \text{NEQN} + 11 \times \text{NEQN}/2 + 1 + \text{nwkres} + \text{lenode}$.

Where

mlu is the lower or upper half bandwidths such that

$\text{mlu} = 3 \times \text{NPDE} - 1$, for PDE problems only (no coupled ODEs); or

$\text{mlu} = \text{NEQN} - 1$, for coupled PDE/ODE problems.

$$\text{nwkres} = \begin{cases} 3 \times (\text{NPOLY} + 1)^2 + (\text{NPOLY} + 1) \times [\text{NPDE}^2 + 6 \times \text{NPDE} + \text{NBKPTS} + 1] + 8 \times \text{NPDE} + \text{NXI} \times (5 \times \text{NPDE} + 1) + \text{NCODE} + 3, & \text{when NCODE} > 0 \text{ and NXI} > 0; \text{ or} \\ 3 \times (\text{NPOLY} + 1)^2 + (\text{NPOLY} + 1) \times [\text{NPDE}^2 + 6 \times \text{NPDE} + \text{NBKPTS} + 1] + 13 \times \text{NPDE} + \text{NCODE} + 4, & \text{when NCODE} > 0 \text{ and NXI} = 0; \text{ or} \\ 3 \times (\text{NPOLY} + 1)^2 + (\text{NPOLY} + 1) \times [\text{NPDE}^2 + 6 \times \text{NPDE} + \text{NBKPTS} + 1] + 13 \times \text{NPDE} + 5, & \text{when NCODE} = 0. \end{cases}$$

$$\text{lenode} = \begin{cases} (6 + \text{int}(\text{ALGOPT}(2))) \times \text{NEQN} + 50, & \text{when the BDF method is used; or} \\ 9 \times \text{NEQN} + 50, & \text{when the Theta method is used.} \end{cases}$$

Note: when LAOPT = 'S', the value of LRSAVE may be too small when supplied to the integrator. An estimate of the minimum size of LRSAVE is printed on the current error message unit if ITRACE > 0 and the routine returns with IFAIL = 15.

27: ISAVE(LISAVE) – INTEGER array *Communication Array*

If IND = 0, ISAVE need not be set on entry.

If IND = 1, ISAVE must be unchanged from the previous call to the routine because it contains required information about the iteration required for subsequent calls. In particular:

ISAVE(1)

Contains the number of steps taken in time.

ISAVE(2)

Contains the number of residual evaluations of the resulting ODE system used. One such evaluation involves computing the PDE functions at all the mesh points, as well as one evaluation of the functions in the boundary conditions.

ISAVE(3)

Contains the number of Jacobian evaluations performed by the time integrator.

ISAVE(4)

Contains the order of the ODE method last used in the time integration.

ISAVE(5)

Contains the number of Newton iterations performed by the time integrator. Each iteration involves residual evaluation of the resulting ODE system followed by a back-substitution using the *LU* decomposition of the Jacobian matrix.

28: LISAVE – INTEGER *Input*

On entry: the dimension of the array ISAVE as declared in the (sub)program from which D03PJF/D03PJA is called. Its size depends on the type of matrix algebra selected:

if LAOPT = 'F', LISAVE \geq 24;

if LAOPT = 'B', LISAVE \geq NEQN + 24;

if LAOPT = 'S', LISAVE \geq 25 \times NEQN + 24.

Note: when using the sparse option, the value of LISAVE may be too small when supplied to the integrator. An estimate of the minimum size of LISAVE is printed on the current error message unit if ITRACE > 0 and the routine returns with IFAIL = 15.

29: ITASK – INTEGER *Input*

On entry: specifies the task to be performed by the ODE integrator.

ITASK = 1

Normal computation of output values U at $t = TOUT$.

ITASK = 2

One step and return.

ITASK = 3

Stop at first internal integration point at or beyond $t = TOUT$.

ITASK = 4

Normal computation of output values U at $t = TOUT$ but without overshooting $t = t_{crit}$ where t_{crit} is described under the parameter ALGOPT.

ITASK = 5

Take one step in the time direction and return, without passing t_{crit} , where t_{crit} is described under the parameter ALGOPT.

Constraint: ITASK = 1, 2, 3, 4 or 5.

30: ITRACE – INTEGER *Input*

On entry: the level of trace information required from D03PJF/D03PJA and the underlying ODE solver. ITRACE may take the value -1 , 0 , 1 , 2 or 3 .

ITRACE = -1

No output is generated.

ITRACE = 0

Only warning messages from the PDE solver are printed on the current error message unit (see X04AAF).

ITRACE > 0

Output from the underlying ODE solver is printed on the current advisory message unit (see X04ABF). This output contains details of Jacobian entries, the nonlinear iteration and the time integration during the computation of the ODE system.

If ITRACE < -1 , then -1 is assumed and similarly if ITRACE > 3 , then 3 is assumed.

The advisory messages are given in greater detail as ITRACE increases. You are advised to set ITRACE = 0 , unless you are experienced with sub-chapter D02M–N.

31: IND – INTEGER *Input/Output*

On entry: indicates whether this is a continuation call or a new integration.

IND = 0

Starts or restarts the integration in time.

IND = 1

Continues the integration after an earlier exit from the routine. In this case, only the parameters TOUT and IFAIL should be reset between calls to D03PJF/D03PJA.

Constraint: IND = 0 or 1 .

On exit: IND = 1 .

32: IFAIL – INTEGER *Input/Output*

Note: for D03PJA, IFAIL does not occur in this position in the parameter list. See the additional parameters described below.

On entry: IFAIL must be set to 0 , -1 or 1 . If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0 . **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

Note: the following are additional parameters for specific use with D03PJA. Users of D03PJF therefore need not read the remainder of this description.

32: IUSER(*) – INTEGER array *User Workspace*

33: RUSER(*) – REAL (KIND=nag_wp) array *User Workspace*

IUSER and RUSER are not used by D03PJF/D03PJA, but are passed directly to PDEDEF, BNDARY, ODEDEF and UVINIT and may be used to pass information to these routines as an alternative to using COMMON global variables.

35:	CWSAV(10) – CHARACTER(80) array	Communication Array
36:	LWSAV(100) – LOGICAL array	Communication Array
37:	IWSAV(505) – INTEGER array	Communication Array
38:	RWSAV(1100) – REAL (KIND=nag_wp) array	Communication Array
38:	IFAIL – INTEGER	Input/Output

Note: see the parameter description for IFAIL above.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, TOUT – TS is too small,
 or ITASK \neq 1, 2, 3, 4 or 5,
 or M \neq 0, 1 or 2,
 or at least one of the coupling point in array XI is outside the interval
 [XBKPTS(1), XBKPTS(NBKPTS)],
 or NPTS \neq (NBKPTS – 1) \times NPOLY + 1,
 or NBKPTS < 2,
 or NPDE \leq 0,
 or NORM \neq 'A' or 'M',
 or ITOL \neq 1, 2, 3 or 4,
 or NPOLY < 1 or NPOLY > 49,
 or NCODE and NXI are incorrectly defined,
 or NEQN \neq NPDE \times NPTS + NCODE,
 or LAOPT \neq 'F', 'B' or 'S',
 or IND \neq 0 or 1,
 or break points XBKPTS(*i*) are badly ordered,
 or LRSAVE is too small,
 or LISAVE is too small,
 or the ODE integrator has not been correctly defined; check ALGOPT parameter,
 or either an element of RTOL or ATOL < 0.0,
 or all the elements of RTOL and ATOL are zero.

IFAIL = 2

The underlying ODE solver cannot make any further progress, with the values of ATOL and RTOL, across the integration range from the current point $t = TS$. The components of U contain the computed values at the current point $t = TS$.

IFAIL = 3

In the underlying ODE solver, there were repeated error test failures on an attempted step, before completing the requested task, but the integration was successful as far as $t = TS$. The problem may have a singularity, or the error requirement may be inappropriate.

IFAIL = 4

In setting up the ODE system, the internal initialization routine was unable to initialize the derivative of the ODE system. This could be due to the fact that IRES was repeatedly set to 3 in at least PDEDEF, BNDARY or ODEDEF, when the residual in the underlying ODE solver was being evaluated.

IFAIL = 5

In solving the ODE system, a singular Jacobian has been encountered. You should check your problem formulation.

IFAIL = 6

When evaluating the residual in solving the ODE system, IRES was set to 2 in at least PDEDEF, BNDARY or ODEDEF. Integration was successful as far as $t = TS$.

IFAIL = 7

The values of ATOL and RTOL are so small that the routine is unable to start the integration in time.

IFAIL = 8

In one of PDEDEF, BNDARY or ODEDEF, IRES was set to an invalid value.

IFAIL = 9 (D02NNF)

A serious error has occurred in an internal call to the specified routine. Check the problem specification and all parameters and array dimensions. Setting ITRACE = 1 may provide more information. If the problem persists, contact NAG.

IFAIL = 10

The required task has been completed, but it is estimated that a small change in ATOL and RTOL is unlikely to produce any change in the computed solution. (Only applies when you are not operating in one step mode, that is when ITASK \neq 2 or 5.)

IFAIL = 11

An error occurred during Jacobian formulation of the ODE system (a more detailed error description may be directed to the current error message unit).

IFAIL = 12

In solving the ODE system, the maximum number of steps specified in ALGOPT(15) have been taken.

IFAIL = 13

Some error weights w_i became zero during the time integration (see the description of ITOL). Pure relative error control ($ATOL(i) = 0.0$) was requested on a variable (the i th) which has become zero. The integration was successful as far as $t = TS$.

IFAIL = 14

The flux function R_i was detected as depending on time derivatives, which is not permissible.

IFAIL = 15

When using the sparse option, the value of LISAVE or LRSAVE was not sufficient (more detailed information may be directed to the current error message unit).

7 Accuracy

D03PJF/D03PJA controls the accuracy of the integration in the time direction but not the accuracy of the approximation in space. The spatial accuracy depends on both the number of mesh points and on their distribution in space. In the time integration only the local error over a single step is controlled and so the accuracy over a number of steps cannot be guaranteed. You should therefore test the effect of varying the accuracy parameter ATOL and RTOL.

8 Further Comments

The parameter specification allows you to include equations with only first-order derivatives in the space direction but there is no guarantee that the method of integration will be satisfactory for such systems. The position and nature of the boundary conditions in particular are critical in defining a stable problem.

The time taken depends on the complexity of the parabolic system and on the accuracy requested.

9 Example

This example provides a simple coupled system of one PDE and one ODE.

$$(V_1)^2 \frac{\partial U_1}{\partial t} - x V_1 \dot{V}_1 \frac{\partial U_1}{\partial x} = \frac{\partial^2 U_1}{\partial x^2}$$

$$\dot{V}_1 = V_1 U_1 + \frac{\partial U_1}{\partial x} + 1 + t,$$

for $t \in [10^{-4}, 0.1 \times 2^i]$, $i = 1, 2, \dots, 5$, $x \in [0, 1]$.

The left boundary condition at $x = 0$ is

$$\frac{\partial U_1}{\partial x} = -V_1 \exp t.$$

The right boundary condition at $x = 1$ is

$$U_1 = -V_1 \dot{V}_1.$$

The initial conditions at $t = 10^{-4}$ are defined by the exact solution:

$$V_1 = t, \quad \text{and} \quad U_1(x, t) = \exp\{t(1-x)\} - 1.0, \quad x \in [0, 1],$$

and the coupling point is at $\xi_1 = 1.0$.

9.1 Program Text

the following program illustrates the use of D03PJF. An equivalent program illustrating the use of D03PJA is available with the supplied Library and is also available from the NAG web site.

```
! D03PJF Example Program Text
! Mark 24 Release. NAG Copyright 2012.

Module d03pjfe_mod

! D03PJF Example Program Module:
! Parameters and User-defined Routines

! .. Use Statements ..
Use nag_library, Only: nag_wp
! .. Implicit None Statement ..
Implicit None
! .. Parameters ..
Real (Kind=nag_wp), Parameter :: one = 1.0_nag_wp
Integer, Parameter :: itrace = 0, ncode = 1, nin = 5, &
nout = 6, npde = 1, nxi = 1

! .. Local Scalars ..
Real (Kind=nag_wp) :: ts
Contains
Subroutine uvinit(npde,npts,x,u,ncode,v)

! Routine for PDE initial values (start time is 0.1D-6)

! .. Scalar Arguments ..
Integer, Intent (In) :: ncode, npde, npts
! .. Array Arguments ..
Real (Kind=nag_wp), Intent (Out) :: u(npde,npts), v(ncode)
Real (Kind=nag_wp), Intent (In) :: x(npts)
! .. Local Scalars ..
Integer :: i
```

```

!      .. Intrinsic Procedures ..
      Intrinsic                               :: exp
!      .. Executable Statements ..
      v(1) = ts
      Do i = 1, npts
        u(1,i) = exp(ts*(one-x(i))) - one
      End Do
      Return
End Subroutine uvinit
Subroutine odedef(npde,t,ncode,v,vdot,nxi,xi,ucp,ucpx,rcp,ucpt,ucptx,f, &
  ires)

!      .. Scalar Arguments ..
      Real (Kind=nag_wp), Intent (In)         :: t
      Integer, Intent (Inout)                 :: ires
      Integer, Intent (In)                    :: ncode, npde, nxi
!      .. Array Arguments ..
      Real (Kind=nag_wp), Intent (Out)        :: f(ncode)
      Real (Kind=nag_wp), Intent (In)         :: rcp(npde,*), ucp(npde,*),      &
        ucpt(npde,*), ucptx(npde,*),      &
        ucpx(npde,*), v(ncode),           &
        vdot(ncode), xi(nxi)

!      .. Executable Statements ..
      If (ires==1) Then
        f(1) = vdot(1) - v(1)*ucp(1,1) - ucpx(1,1) - one - t
      Else If (ires== -1) Then
        f(1) = vdot(1)
      End If
      Return
End Subroutine odedef
Subroutine pdedef(npde,t,x,nptl,u,ux,ncode,v,vdot,p,q,r,ires)

!      .. Scalar Arguments ..
      Real (Kind=nag_wp), Intent (In)         :: t
      Integer, Intent (Inout)                 :: ires
      Integer, Intent (In)                    :: ncode, npde, nptl
!      .. Array Arguments ..
      Real (Kind=nag_wp), Intent (Out)        :: p(npde,npde,nptl),           &
        q(npde,nptl), r(npde,nptl)
      Real (Kind=nag_wp), Intent (In)         :: u(npde,nptl), ux(npde,nptl),   &
        v(ncode), vdot(ncode), x(nptl)

!      .. Local Scalars ..
      Integer                                  :: i
!      .. Executable Statements ..
      Do i = 1, nptl
        p(1,1,i) = v(1)*v(1)
        r(1,i) = ux(1,i)
        q(1,i) = -x(i)*ux(1,i)*v(1)*vdot(1)
      End Do
      Return
End Subroutine pdedef
Subroutine bndary(npde,t,u,ux,ncode,v,vdot,ibnd,beta,gamma,ires)

!      .. Scalar Arguments ..
      Real (Kind=nag_wp), Intent (In)         :: t
      Integer, Intent (In)                    :: ibnd, ncode, npde
      Integer, Intent (Inout)                 :: ires
!      .. Array Arguments ..
      Real (Kind=nag_wp), Intent (Out)        :: beta(npde), gamma(npde)
      Real (Kind=nag_wp), Intent (In)         :: u(npde), ux(npde), v(ncode),   &
        vdot(ncode)

!      .. Intrinsic Procedures ..
      Intrinsic                               :: exp
!      .. Executable Statements ..
      beta(1) = 1.0E0_nag_wp
      If (ibnd==0) Then
        gamma(1) = -v(1)*exp(t)
      Else
        gamma(1) = -v(1)*vdot(1)
      End If
      Return

```

```

End Subroutine bndary
Subroutine exact(time,npts,x,u)
!   Exact solution (for comparison purposes)

!   .. Scalar Arguments ..
Real (Kind=nag_wp), Intent (In)      :: time
Integer, Intent (In)                 :: npts
!   .. Array Arguments ..
Real (Kind=nag_wp), Intent (Out)     :: u(npts)
Real (Kind=nag_wp), Intent (In)      :: x(npts)
!   .. Local Scalars ..
Integer                               :: i
!   .. Intrinsic Procedures ..
Intrinsic                             :: exp
!   .. Executable Statements ..
Do i = 1, npts
    u(i) = exp(time*(one-x(i))) - one
End Do
Return
End Subroutine exact
End Module d03pjfe_mod
Program d03pjfe

!   D03PJF Example Main Program

!   .. Use Statements ..
Use nag_library, Only: d03pjf, nag_wp
Use d03pjfe_mod, Only: bndary, exact, itrace, ncode, nin, nout, npde, &
    nxi, odedef, pdedef, ts, uvinit
!   .. Implicit None Statement ..
Implicit None
!   .. Local Scalars ..
Real (Kind=nag_wp)                  :: tout
Integer                             :: i, ifail, ind, it, itask, itol, &
    latol, lenode, lisave, lrsave, &
    lrtol, m, nbkpts, nel, neqn, &
    npl, npoly, npts, nwkres

Logical                             :: theta
Character (1)                       :: laopt, norm
!   .. Local Arrays ..
Real (Kind=nag_wp)                  :: algopt(30), xi(nxi)
Real (Kind=nag_wp), Allocatable     :: atol(:), exy(:), rsave(:), &
    rtol(:), u(:), x(:), xbkpts(:)
Integer, Allocatable                 :: isave(:)
!   .. Intrinsic Procedures ..
Intrinsic                             :: mod, real
!   .. Executable Statements ..
Write (nout,*) 'D03PJF Example Program Results'
!   Skip heading in data file
Read (nin,*)
Read (nin,*) m, nbkpts, npoly

nel = nbkpts - 1
npts = nel*npoly + 1
neqn = npde*npts + ncode
npl = npoly + 1
nwkres = npl*(3*npl+npde*npde+6*npde+nbkpts+1)
nwkres = nwkres + 8*npde + nxi*(5*npde+1) + ncode + 3
lenode = 11*neqn + 50
lisave = 25*neqn + 24
lrsave = neqn*neqn + neqn + nwkres + lenode
Allocate (exy(nbkpts),u(neqn),rsave(lrsave),x(npts),xbkpts(nbkpts), &
    isave(lisave))

Read (nin,*) itol
latol = 1
lrtol = 1
If (itol>2) latol = neqn
If (mod(itol,2)==0) lrtol = neqn
Allocate (atol(latol),rtol(lrtol))
Read (nin,*) atol(1:latol), rtol(1:lrtol)

```

```

      Read (nin,*) ts

!      Set break-points
      Do i = 1, nbkpts
         xbkpts(i) = real(i-1,kind=nag_wp)/real(nbkpts-1,kind=nag_wp)
      End Do

      Read (nin,*) xi(1:nxi)
      Read (nin,*) norm, laopt
      ind = 0
      itask = 1

!      Set theta to .TRUE. if the Theta integrator is required
      theta = .False.
      algopt(1:30) = 0.0_nag_wp
      If (theta) Then
         algopt(1) = 2.0_nag_wp
      End If

!      Loop over output value of t

      tout = 0.2_nag_wp
      Do it = 1, 5

!         ifail: behaviour on error exit
!         =0 for hard exit, =1 for quiet-soft, =-1 for noisy-soft
         ifail = 0
         Call d03pjf(npde,m,ts,tout,pdedef,bndary,u,nbkpts,xbkpts,npoly,npts,x, &
            ncode,odedef,nxi,xi,neqn,uvinit,rtol,atol,itol,norm,laopt,algot, &
            rsave,lrsave,isave,lisave,itask,itrace,ind,ifail)

         If (it==1) Then
            Write (nout,99999) npoly, nel
            Write (nout,99996) atol, npts
            Write (nout,99998)(xbkpts(i),i=1,7,2), xbkpts(nbkpts)
         End If

!         Check against the exact solution at alternate breakpoints.
         Call exact(tout,nbkpts,xbkpts,exy)
         Write (nout,99997) ts
         Write (nout,99994)(u(i),i=1,6*npoly+1,2*npoly), u(npts:neqn)
         Write (nout,99993)(exy(i),i=1,7,2), exy(nbkpts), ts
         tout = 2.0E0_nag_wp*tout
      End Do
      Write (nout,99995) isave(1), isave(2), isave(3), isave(5)

99999 Format (' Degree of Polynomial =',I4,'   No. of elements =',I4/)
99998 Format ('   X           ',5F9.3/)
99997 Format (' T = ',F6.3)
99996 Format (/'/' Simple coupled PDE using BDF '/' Accuracy require', &
   'ment =',E10.3,' Number of points = ',I4/)
99995 Format (' Number of integration steps in time = ',I6/' Number o', &
   'f function evaluations = ',I6/' Number of Jacobian eval', 'uations =', &
   I6/' Number of iterations = ',I6)
99994 Format (1X,'App. sol. ',F7.3,4F9.3,' ODE sol. =',F8.3)
99993 Format (1X,'Exact sol. ',F7.3,4F9.3,' ODE sol. =',F8.3/)
      End Program d03pjfe

```

9.2 Program Data

D03PJF Example Program Data

0	11	2	:	m, nbkpts, npoly
1			:	itol
1.0E-4	1.0E-4		:	atol(1), rtol(1)
1.0E-4			:	ts
1.0			:	xi(1:nxi)
A	F		:	norm, laopt

9.3 Program Results

D03PJF Example Program Results

Degree of Polynomial = 2 No. of elements = 10

Simple coupled PDE using BDF

Accuracy requirement = 0.100E-03 Number of points = 21

x	0.000	0.200	0.400	0.600	1.000		
T = 0.200							
App. sol.	0.222	0.174	0.128	0.084	0.000	ODE sol. =	0.200
Exact sol.	0.221	0.174	0.127	0.083	0.000	ODE sol. =	0.200
T = 0.400							
App. sol.	0.492	0.378	0.272	0.174	0.000	ODE sol. =	0.400
Exact sol.	0.492	0.377	0.271	0.174	0.000	ODE sol. =	0.400
T = 0.800							
App. sol.	1.226	0.897	0.616	0.377	0.000	ODE sol. =	0.800
Exact sol.	1.226	0.896	0.616	0.377	0.000	ODE sol. =	0.800
T = 1.600							
App. sol.	3.954	2.597	1.611	0.896	-0.001	ODE sol. =	1.600
Exact sol.	3.953	2.597	1.612	0.896	0.000	ODE sol. =	1.600
T = 3.200							
App. sol.	23.534	11.931	5.815	2.590	-0.008	ODE sol. =	3.202
Exact sol.	23.533	11.936	5.821	2.597	0.000	ODE sol. =	3.200

Number of integration steps in time = 34

Number of function evaluations = 497

Number of Jacobian evaluations = 17

Number of iterations = 112

Example Program
Parabolic PDE Coupled with ODE using Collocation and BDF

