

## NAG Toolbox

### nag\_ode\_ivp\_adams\_roots\_revcom (d02qg)

#### 1 Purpose

nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) is a reverse communication function for integrating a non-stiff system of first-order ordinary differential equations using a variable-order variable-step Adams' method. A root-finding facility is provided.

#### 2 Syntax

```
[t, y, root, irevcm, trvcm, yrvcm, yprvcm, kgrvcm, rwork, iwork, ifail] =
nag_ode_ivp_adams_roots_revcom(t, y, tout, neqq, irevcm, grvcm, kgrvcm, rwork,
iwork, 'neqf', neqf)

[t, y, root, irevcm, trvcm, yrvcm, yprvcm, kgrvcm, rwork, iwork, ifail] = d02qg
(t, y, tout, neqq, irevcm, grvcm, kgrvcm, rwork, iwork, 'neqf', neqf)
```

**Note:** the interface to this routine has changed since earlier releases of the toolbox:

At Mark 22: *lwork* and *liwork* were removed from the interface.

#### 3 Description

Given the initial values  $x, y_1, y_2, \dots, y_{\mathbf{neqf}}$  nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) integrates a non-stiff system of first-order differential equations of the type

$$y'_i = f_i(x, y_1, y_2, \dots, y_{\mathbf{neqf}}), \quad i = 1, 2, \dots, \mathbf{neqf},$$

from  $x = \mathbf{t}$  to  $x = \mathbf{tout}$  using a variable-order variable-step Adams' method. You define the system by reverse communication, evaluating  $f_i$  in terms of  $x$  and  $y_1, y_2, \dots, y_{\mathbf{neqf}}$ , and  $y_1, y_2, \dots, y_{\mathbf{neqf}}$  are supplied at  $x = \mathbf{t}$  by nag\_ode\_ivp\_adams\_roots\_revcom (d02qg). The function is capable of finding roots (values of  $x$ ) of prescribed event functions of the form

$$g_j(x, y, y') = 0, \quad j = 1, 2, \dots, \mathbf{neqq}.$$

Each  $g_j$  is considered to be independent of the others so that roots are sought of each  $g_j$  individually. The root reported by the function will be the first root encountered by any  $g_j$ . Two techniques for determining the presence of a root in an integration step are available: the sophisticated method described in Watts (1985) and a simplified method whereby sign changes in each  $g_j$  are looked for at the ends of each integration step. You also define each  $g_j$  by reverse communication. In one-step mode the function returns an approximation to the solution at each integration point. In interval mode this value is returned at the end of the integration range. If a root is detected this approximation is given at the root. You select the mode of operation, the error control, the root-finding technique and various optional inputs by a prior call to the setup function nag\_ode\_ivp\_adams\_setup (d02qw).

For a description of the practical implementation of an Adams' formula see Shampine and Gordon (1975).

## 4 References

Shampine L F and Gordon M K (1975) *Computer Solution of Ordinary Differential Equations – The Initial Value Problem* W H Freeman & Co., San Francisco

Shampine L F and Watts H A (1979) DEPAC – design of a user oriented package of ODE solvers *Report SAND79-2374* Sandia National Laboratory

Watts H A (1985) RDEAM – An Adams ODE code with root solving capability *Report SAND85-1595* Sandia National Laboratory

## 5 Parameters

**Note:** this function uses **reverse communication**. Its use involves an initial entry, intermediate exits and re-entries, and a final exit, as indicated by the argument **irevcm**. Between intermediate exits and re-entries, **all arguments other than grvcm and rwork must remain unchanged**.

### 5.1 Compulsory Input Parameters

1: **t** – REAL (KIND=nag\_wp)

*On initial entry:* that is after a call to nag\_ode\_ivp\_adams\_setup (d02qw) with **statef** = 'S', **t** must be set to the initial value of the independent variable  $x$ .

2: **y(neqf)** – REAL (KIND=nag\_wp) array

*On initial entry:* the initial values of the solution  $y_1, y_2, \dots, y_{neqf}$ .

3: **tout** – REAL (KIND=nag\_wp)

*On initial entry:* the next value of  $x$  at which a computed solution is required. For the initial **t**, the input value of **tout** is used to determine the direction of integration. Integration is permitted in either direction. If **tout** = **t** on exit, **tout** must be reset beyond **t** in the direction of integration, before any continuation call.

4: **neqg** – INTEGER

*On initial entry:* the number of event functions which you are defining for root-finding. If root-finding is not required the value for **neqg** must be  $\leq 0$ . Otherwise it must be the same value as the argument **neqg** used in the prior call to nag\_ode\_ivp\_adams\_setup (d02qw).

5: **irevcm** – INTEGER

*On initial entry:* must have the value 0.

6: **grvcm** – REAL (KIND=nag\_wp)

*On initial entry:* need not be set.

*On intermediate re-entry:* with **irevcm** = 9, 10, 11 or 12, **grvcm** must contain the value of  $g_k(x, y, y')$ , where  $k$  is given by **kgvcm**.

7: **kgvcm** – INTEGER

*On intermediate re-entry:* with **irevcm** = 9, 10, 11 or 12, **kgvcm** must remain unchanged from a previous call to nag\_ode\_ivp\_adams\_roots\_revcom (d02qg).

8: **rwork**(*lwork*) – REAL (KIND=nag\_wp) array

This **must** be the same argument **rwork** as supplied to nag\_ode\_ivp\_adams\_setup (d02qw). It is used to pass information from nag\_ode\_ivp\_adams\_setup (d02qw) to nag\_ode\_ivp\_adams\_roots\_revcom (d02qg), and from nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) to nag\_ode\_ivp\_adams\_diag (d02qx), nag\_ode\_ivp\_adams\_rootdiag (d02qy) and nag\_ode\_ivp\_adams\_interp

(d02qz). Therefore the contents of this array **must not** be changed before the call to nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) or calling any of the functions nag\_ode\_ivp\_adams\_diag (d02qx), nag\_ode\_ivp\_adams\_rootdiag (d02qy) and nag\_ode\_ivp\_adams\_interp (d02qz).

- 9: **iwork**(*liwork*) – INTEGER array

This **must** be the same argument **iwork** as supplied to nag\_ode\_ivp\_adams\_setup (d02qw). It is used to pass information from nag\_ode\_ivp\_adams\_setup (d02qw) to nag\_ode\_ivp\_adams\_roots\_revcom (d02qg), and from nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) to nag\_ode\_ivp\_adams\_diag (d02qx), nag\_ode\_ivp\_adams\_rootdiag (d02qy) and nag\_ode\_ivp\_adams\_interp (d02qz). Therefore the contents of this array **must not** be changed before the call to nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) or calling any of the functions nag\_ode\_ivp\_adams\_diag (d02qx), nag\_ode\_ivp\_adams\_rootdiag (d02qy) and nag\_ode\_ivp\_adams\_interp (d02qz).

## 5.2 Optional Input Parameters

- 1: **neqf** – INTEGER

*Default:* the dimension of the array **y**.

*On initial entry:* the number of first-order ordinary differential equations to be solved by nag\_ode\_ivp\_adams\_roots\_revcom (d02qg). It must contain the same value as the argument **neqf** used in the prior call to nag\_ode\_ivp\_adams\_setup (d02qw).

*Constraint:* **neqf**  $\geq$  1.

## 5.3 Output Parameters

- 1: **t** – REAL (KIND=nag\_wp)

*On final exit:* the value of  $x$  at which  $y$  has been computed. This may be an intermediate output point, a root, **tout** or a point at which an error has occurred. If the integration is to be continued, possibly with a new value for **tout**, **t** must not be changed.

- 2: **y(neqf)** – REAL (KIND=nag\_wp) array

*On final exit:* the computed values of the solution at the exit value of **t**. If the integration is to be continued, possibly with a new value for **tout**, these values must not be changed.

- 3: **root** – LOGICAL

*On final exit:* if root-finding was required (**neqg**  $>$  0 on entry), then **root** specifies whether or not the output value of the argument **t** is a root of one of the event functions. If **root** = *false*, then no root was detected, whereas **root** = *true* indicates a root and you should make a call to nag\_ode\_ivp\_adams\_rootdiag (d02qy) for further information.

If root-finding was not required (**neqg** = 0 on entry), then **root** = *false*.

- 4: **irevcm** – INTEGER

*On intermediate exit:* specifies what action you must take before re-entering nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) **with irevcm unchanged**.

**irevcm** = 1, 2, 3, 4, 5, 6 or 7

Indicates that you must supply  $y' = f(x, y)$ , where  $x$  is given by **trvcm** and  $y_i$  is returned in **y**( $i$ ), for  $i = 1, 2, \dots, \text{neqf}$  when **yrvcm** = 0 and **rwork**(**yrvcm** +  $i - 1$ ), for  $i = 1, 2, \dots, \text{neqf}$  when **yrvcm**  $\neq$  0.  $y'_i$  should be placed in location **rwork**(**yprvcm** +  $i - 1$ ), for  $i = 1, 2, \dots, \text{neqf}$ .

**irevcm** = 8

Indicates that the current step was not successful due to error test failure. The only information supplied to you on this return is the current value of the independent variable **t**, as given by **trvcm**. No values must be changed before re-entering nag\_ode\_ivp\_adams\_

roots\_revcom (d02qg). This facility enables you to determine the number of unsuccessful steps.

**irevcm** = 9, 10, 11 or 12

Indicates that you must supply  $g_k(x, y, y')$ , where  $k$  is given by **kgrvcm**,  $x$  is given by **trvcm**,  $y_i$  is given by **y(i)** and  $y'_i$  is given by **rwork(yprvcm - 1 + i)**. The result  $g_k$  should be placed in the variable **grvcm**.

*On final exit:* has the value 0, which indicates that an output point or root has been reached or an error has occurred (see **ifail**).

5: **trvcm** – REAL (KIND=nag\_wp)

*On intermediate exit:* the current value of the independent variable.

6: **yrvcm** – INTEGER

*On intermediate exit:* with **irevcm** = 1, 2, 3, 4, 5, 6, 7, 9, 10, 11 or 12, **yrvcm** specifies the locations of the dependent variables  $y$  for use in evaluating the differential system or the event functions.

**yrvcm** = 0

$y_i$  is given by **y(i)**, for  $i = 1, 2, \dots, \mathbf{neqf}$ .

**yrvcm**  $\neq$  0

$y_i$  is given by **rwork(yrvcm + i - 1)**, for  $i = 1, 2, \dots, \mathbf{neqf}$ .

7: **yprvcm** – INTEGER

*On intermediate exit:* with **irevcm** = 1, 2, 3, 4, 5, 6 or 7, **yprvcm** specifies the positions in **rwork** at which you should place the derivatives  $y'$ .  $y'_i$  should be placed in location **rwork(yprvcm + i - 1)**, for  $i = 1, 2, \dots, \mathbf{neqf}$ .

With **irevcm** = 9, 10, 11 or 12, **yprvcm** specifies the locations of the derivatives  $y'$  for use in evaluating the event functions.  $y'_i$  is given by **rwork(yprvcm + i - 1)**, for  $i = 1, 2, \dots, \mathbf{neqf}$ .

8: **kgrvcm** – INTEGER

*On intermediate exit:* with **irevcm** = 9, 10, 11 or 12, **kgrvcm** specifies which event function  $g_k(x, y, y')$  you must evaluate.

9: **rwork(lrwork)** – REAL (KIND=nag\_wp) array

10: **iwork(liwork)** – INTEGER array

11: **ifail** – INTEGER

*On final exit:* **ifail** = 0 unless the function detects an error (see Section 5).

## 6 Error Indicators and Warnings

Errors or warnings detected by the function:

**ifail** = 1

On entry, the integrator detected an illegal input, or nag\_ode\_ivp\_adams\_setup (d02qw) has not been called before the call to the integrator.

This error may be caused by overwriting elements of **rwork** and **iwork**.

**ifail** = 2 (*warning*)

The maximum number of steps has been attempted (at a cost of about 2 derivative evaluations per step). (See argument **maxstp** in nag\_ode\_ivp\_adams\_setup (d02qw).) If integration is to be

continued then you need only reset **ifail** and call the function again and a further **maxstp** steps will be attempted.

**ifail** = 3

The step size needed to satisfy the error requirements is too small for the *machine precision* being used. (See argument **tolfac** in nag\_ode\_ivp\_adams\_diag (d02qx).)

**ifail** = 4 (*warning*)

Some error weight  $w_i$  became zero during the integration (see arguments **vectol**, **rtol** and **atol** in nag\_ode\_ivp\_adams\_setup (d02qw).) Pure relative error control (**atol** = 0.0) was requested on a variable (the  $i$ th) which has now become zero. (See argument **badcmp** in nag\_ode\_ivp\_adams\_diag (d02qx).) The integration was successful as far as **t**.

**ifail** = 5 (*warning*)

The problem appears to be stiff (see the D02 Chapter Introduction for a discussion of the term ‘stiff’). Although it is inefficient to use this integrator to solve stiff problems, integration may be continued by resetting **ifail** and calling the function again.

**ifail** = 6 (*warning*)

A change in sign of an event function has been detected but the root-finding process appears to have converged to a singular point **t** rather than a root. Integration may be continued by resetting **ifail** and calling the function again.

**ifail** = 7

The code has detected two successive error exits at the current value of **t** and cannot proceed. Check all input variables.

**ifail** = -99

An unexpected error has been triggered by this routine. Please contact NAG.

**ifail** = -399

Your licence key may have expired or may not have been installed correctly.

**ifail** = -999

Dynamic memory allocation failed.

## 7 Accuracy

The accuracy of integration is determined by the arguments **vectol**, **rtol** and **atol** in a prior call to nag\_ode\_ivp\_adams\_setup (d02qw). Note that only the local error at each step is controlled by these arguments. The error estimates obtained are not strict bounds but are usually reliable over one step. Over a number of steps the overall error may accumulate in various ways, depending on the properties of the differential equation system. The code is designed so that a reduction in the tolerances should lead to an approximately proportional reduction in the error. You are strongly recommended to call nag\_ode\_ivp\_adams\_roots\_revcom (d02qg) with more than one set of tolerances and to compare the results obtained to estimate their accuracy.

The accuracy obtained depends on the type of error test used. If the solution oscillates around zero a relative error test should be avoided, whereas if the solution is exponentially increasing an absolute error test should not be used. If different accuracies are required for different components of the solution then a component-wise error test should be used. For a description of the error test see the specifications of the arguments **vectol**, **rtol** and **atol** in the function document for nag\_ode\_ivp\_adams\_setup (d02qw).

The accuracy of any roots located will depend on the accuracy of integration and may also be restricted by the numerical properties of  $g(x, y, y')$ . When evaluating  $g$  you should try to write the code so that unnecessary cancellation errors will be avoided.

## 8 Further Comments

If `nag_ode_ivp_adams_roots_revcom` (d02qg) fails with `ifail = 3` then the combination of `atol` and `rtol` may be so small that a solution cannot be obtained, in which case the function should be called again with larger values for `rtol` and/or `atol` (see `nag_ode_ivp_adams_setup` (d02qw)). If the accuracy requested is really needed then you should consider whether there is a more fundamental difficulty. For example:

- (a) in the region of a singularity the solution components will usually be of a large magnitude. `nag_ode_ivp_adams_roots_revcom` (d02qg) could be used in one-step mode to monitor the size of the solution with the aim of trapping the solution before the singularity. In any case numerical integration cannot be continued through a singularity, and analytical treatment may be necessary;
- (b) for ‘stiff’ equations, where the solution contains rapidly decaying components, the function will require a very small step size to preserve stability. This will usually be exhibited by excessive computing time and sometimes an error exit with `ifail = 3`, but usually an error exit with `ifail = 2` or 5. The Adams' methods are not efficient in such cases and you should consider using a function from the Sub-chapter D02M–N. A high proportion of failed steps (see argument `nfail` in `nag_ode_ivp_adams_diag` (d02qx)) may indicate stiffness but there may be other reasons for this phenomenon.

`nag_ode_ivp_adams_roots_revcom` (d02qg) can be used for producing results at short intervals (for example, for graph plotting); you should set `crit = true` and `tcrit` to the last output point required in a prior call to `nag_ode_ivp_adams_setup` (d02qw) and then set `tout` appropriately for each output point in turn in the call to `nag_ode_ivp_adams_roots_revcom` (d02qg).

## 9 Example

This example solves the following system (for a projectile)

$$\begin{aligned} y' &= \tan \phi \\ v' &= \frac{-0.032 \tan \phi}{v} - \frac{0.02v}{\cos \phi} \\ \phi' &= \frac{-0.032}{v^2} \end{aligned}$$

over an interval [0.0, 10.0] starting with values  $y = 0.5$ ,  $v = 0.5$  and  $\phi = \pi/5$  using scalar error control (`vectol = false`) until the first point where  $y = 0.0$  is encountered.

Also, `nag_ode_ivp_adams_roots_revcom` (d02qg) is used to produce output at intervals of 2.0.

### 9.1 Program Text

```
function d02qg_example
fprintf('d02qg example results\n\n');

% Initialize setup variables and arrays.
statef = 'S';
neqf   = nag_int(3);
vectol = false;
atol   = [1e-4];
rtol   = [1e-7];
onestp = false;
crit   = true;
tcrit  = 10;
hmax   = 2;
maxstp = nag_int(500);
neqg   = nag_int(1);
alterg = false;
```

```

sophst = true;
rwork = zeros(106, 1);
iwork = zeros(25, 1, nag_int_name);

% d02qw is a setup routine to be called prior to d02qg.
[statef, alterg, rwork, iwork, ifail] = ...
    d02qw(...
        statef, neqf, vectol, atol, rtol, onestp, crit, tcrit, ...
        hmax, maxstp, neqg, alterg, sophst, rwork, iwork);

%Initialize integrator input variables
t = 0;
y = [0.5; 0.5; 0.2*pi];
grv = 0;
kgrv = nag_int(0);

% Initialize output variables and arrays.
tinc = 2;
ncall = 1;
tkeep = zeros(1,1);
ykeep = zeros(1,neqf);

% Output initial results, then store them for plotting.
fprintf(' t      y(1)      y(2)      y(3)\n');
fprintf('%7.4f %7.4f %7.4f %7.4f\n', t, y(1), y(2), y(3));
tkeep(ncall) = t;
ykeep(ncall,:) = y;

for j=1:5

    tout = double(j)*tinc;
    % Initial call of d02qg for this t value.
    irevcm = nag_int(0);
    first_call = true;

    % d02qg uses reverse communication. Keep re-entering the function
    % until a final exit (irevcm = 0) occurs.
    while (irevcm ~= 0 || first_call)
        first_call = false;
        [t, y, root, irevcm, trv, yrv, yprv, kgrv, rwork, iwork, ifail] = ...
            d02qg(...
                t, y, tout, neqg, irevcm, grv, kgrv, rwork, iwork);
        if (irevcm > 0 && irevcm < 8)
            % Set current values for derivatives.
            if (yrv == 0)
                rwork(yprv) = tan(y(3));
                rwork(yprv+1) = -0.032*tan(y(3))/y(2) - 0.02*y(2)/cos(y(3));
                rwork(yprv+2) = -0.032/y(2)^2;
            else
                y2 = rwork(yrv+1);
                y3 = rwork(yrv+2);
                rwork(yprv) = tan(y3);
                rwork(yprv+1) = -0.032*tan(y3)/y2 - 0.02*y2/cos(y3);
                rwork(yprv+2) = -0.032/y2^2;
            end
        elseif (irevcm > 8)
            grv = y(1);
        end
    end

    % Output results, then store them for plotting.
    fprintf('%7.4f %7.4f %7.4f %7.4f\n', t, y(1), y(2), y(3));
    ncall = ncall + 1;
    tkeep(ncall) = t;
    ykeep(ncall,:) = y;
end

% Plot results.
fig1 = figure;
display_plot(tkeep, ykeep)

function display_plot(tkeep, ykeep)

```

```

% Plot the results.
plot(tkeep, ykeep(:,1), '-+', tkeep, ykeep(:,2), '--x', tkeep, ...
     ykeep(:,3), '*');
%Add title.
title('ODE Solution using Adams Method with Root-finding');
% Label the axes.
xlabel('x');
ylabel('Solution');
% Add a legend.
legend('height','velocity','angle','Location','Best');

```

## 9.2 Program Results

d02qg example results

t	y(1)	y(2)	y(3)
0.0000	0.5000	0.5000	0.6283
2.0000	1.5493	0.4055	0.3066
4.0000	1.7424	0.3743	-0.1289
6.0000	1.0058	0.4173	-0.5507
7.2879	-0.0000	0.4749	-0.7601
10.0000	-3.6287	0.6333	-1.0515

