

NAG Library Function Document

nag_real_sparse_eigensystem_option (f12adc)

Note: this function uses **optional parameters** to define choices in the problem specification. If you wish to use default settings for all of the optional parameters, then this function need not be called. If, however, you wish to reset some or all of the settings please refer to Section 11 for a detailed description of the specification of the optional parameters.

1 Purpose

nag_real_sparse_eigensystem_option (f12adc) is an option setting function that may be used to supply individual optional parameters to nag_real_sparse_eigensystem_iter (f12abc) and nag_real_sparse_eigensystem_sol (f12acc). These are part of a suite of functions that also includes: nag_real_sparse_eigensystem_init (f12aac) and nag_real_sparse_eigensystem_monit (f12aec). The initialization function nag_real_sparse_eigensystem_init (f12aac) **must** have been called prior to calling nag_real_sparse_eigensystem_option (f12adc).

2 Specification

```
#include <nag.h>
#include <nagf12.h>

void nag_real_sparse_eigensystem_option (const char *str, Integer icomm[],
                                         double comm[], NagError *fail)
```

3 Description

nag_real_sparse_eigensystem_option (f12adc) may be used to supply values for optional parameters to nag_real_sparse_eigensystem_iter (f12abc) and nag_real_sparse_eigensystem_sol (f12acc). It is only necessary to call nag_real_sparse_eigensystem_option (f12adc) for those arguments whose values are to be different from their default values. One call to nag_real_sparse_eigensystem_option (f12adc) sets one argument value.

Each optional parameter is defined by a single character string consisting of one or more items. The items associated with a given option must be separated by spaces, or equals signs [=]. Alphabetic characters may be upper or lower case. The string

```
Vectors = None
```

is an example of a string used to set an optional parameter. For each option the string contains one or more of the following items:

- a mandatory keyword;
- a phrase that qualifies the keyword;
- a number that specifies an Integer or double value. Such numbers may be up to 16 contiguous characters in C's d or g format.

nag_real_sparse_eigensystem_option (f12adc) does not have an equivalent function from the ARPACK package which passes options by directly setting values to scalar arguments or to specific elements of array arguments. nag_real_sparse_eigensystem_option (f12adc) is intended to make the passing of options more transparent and follows the same principle as the single option setting functions in Chapter e04.

The setup function nag_real_sparse_eigensystem_init (f12aac) must be called prior to the first call to nag_real_sparse_eigensystem_option (f12adc) and all calls to nag_real_sparse_eigensystem_option (f12adc) must precede the first call to nag_real_sparse_eigensystem_iter (f12abc), the reverse communication iterative solver.

A complete list of optional parameters, their abbreviations, synonyms and default values is given in Section 11.

4 References

Lehoucq R B (2001) Implicitly restarted Arnoldi methods and subspace iteration *SIAM Journal on Matrix Analysis and Applications* **23** 551–562

Lehoucq R B and Scott J A (1996) An evaluation of software for computing eigenvalues of sparse nonsymmetric matrices *Preprint MCS-P547-1195* Argonne National Laboratory

Lehoucq R B and Sorensen D C (1996) Deflation techniques for an implicitly restarted Arnoldi iteration *SIAM Journal on Matrix Analysis and Applications* **17** 789–821

Lehoucq R B, Sorensen D C and Yang C (1998) *ARPACK Users' Guide: Solution of Large-scale Eigenvalue Problems with Implicitly Restarted Arnoldi Methods* SIAM, Philadelphia

5 Arguments

- 1: **str** – const char * *Input*
On entry: a single valid option string (as described in Section 3 and Section 11).

- 2: **icomm**[*dim*] – Integer *Communication Array*
Note: the dimension, *dim*, of the array **icomm** must be at least $\max(1, \mathbf{licomm})$ (see `nag_real_sparse_eigensystem_init` (f12aac)).
On initial entry: must remain unchanged following a call to the setup function `nag_real_sparse_eigensystem_init` (f12aac).
On exit: contains data on the current options set.

- 3: **comm**[*dim*] – double *Communication Array*
Note: the dimension, *dim*, of the array **comm** must be at least 60.
On initial entry: must remain unchanged following a call to the setup function `nag_real_sparse_eigensystem_init` (f12aac).
On exit: contains data on the current options set.

- 4: **fail** – NagError * *Input/Output*
The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.

See Section 2.3.1.2 in How to Use the NAG Library and its Documentation for further information.

NE_BAD_PARAM

On entry, argument *<value>* had an illegal value.

NE_INITIALIZATION

Either the initialization function has not been called prior to the call of this function or a communication array has become corrupted.

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please contact NAG for assistance.

An unexpected error has been triggered by this function. Please contact NAG.
See Section 2.7.6 in How to Use the NAG Library and its Documentation for further information.

NE_INVALID_OPTION

Ambiguous keyword: $\langle value \rangle$

Keyword not recognized: $\langle value \rangle$

Second keyword not recognized: $\langle value \rangle$

NE_NO_LICENCE

Your licence key may have expired or may not have been installed correctly.
See Section 2.7.5 in How to Use the NAG Library and its Documentation for further information.

7 Accuracy

Not applicable.

8 Parallelism and Performance

nag_real_sparse_eigensystem_option (f12adc) is not threaded in any implementation.

9 Further Comments

None.

10 Example

This example solves $Ax = \lambda Bx$ in shifted-inverse mode, where A and B are derived from the finite element discretization of the one-dimensional convection-diffusion operator $\frac{d^2u}{dx^2} + \rho \frac{du}{dx}$ on the interval $[0, 1]$, with zero Dirichlet boundary conditions.

The shift σ is a real number, and the operator used in the shifted-inverse iterative process is $OP = (A - \sigma B)^{-1}B$.

10.1 Program Text

```
/* nag_real_sparse_eigensystem_option (f12adc) Example Program.
 *
 * NAGPRODCODE Version.
 *
 * Copyright 2016 Numerical Algorithms Group.
 *
 * Mark 26, 2016.
 */

#include <math.h>
#include <nag.h>
#include <nag_stdlib.h>
#include <stdio.h>
#include <nagf12.h>
#include <nagf16.h>

static void mv(Integer, double *, double *);
static void my_dgttrf(Integer, double *, double *, double *,
                    double *, Integer *, Integer *);
static void my_dgttrs(Integer, double *, double *, double *,
```

```

double *, Integer *, double *, double *);

int main(void)
{
    /* Constants */
    Integer licomm = 140, imon = 0;
    /* Scalars */
    double estnrm, h, rho, s, s1, s2, s3, sigmai, sigmar;
    Integer exit_status, info, irevcm, j, lcomm, n, nconv, ncv;
    Integer nev, niter, nshift, nx;
    /* Nag types */
    NagError fail;

    /* Arrays */
    double *comm = 0, *dd = 0, *dl = 0, *du = 0, *du2 = 0, *eigvr = 0;
    double *eigvi = 0, *eigest = 0, *resid = 0, *x2 = 0, *v = 0;
    Integer *icomm = 0, *ipiv = 0;
    /* Pointers */
    double *mx = 0, *x = 0, *y = 0;

    exit_status = 0;
    INIT_FAIL(fail);

    printf("nag_real_sparse_eigensystem_option (f12adc) Example "
           "Program Results\n");
    /* Skip heading in data file */
#ifdef _WIN32
    scanf_s("%*[\n] ");
#else
    scanf("%*[\n] ");
#endif
    /* Read problem parameter values from data file. */
#ifdef _WIN32
    scanf_s("%" NAG_IFMT "%" NAG_IFMT "%" NAG_IFMT "%lf%lf%lf%*[\n] ", &nx,
            &nev, &ncv, &rho, &sigmar, &sigmai);
#else
    scanf("%" NAG_IFMT "%" NAG_IFMT "%" NAG_IFMT "%lf%lf%lf%*[\n] ", &nx, &nev,
            &ncv, &rho, &sigmar, &sigmai);
#endif
    n = nx * nx;
    lcomm = 3 * n + 3 * ncv * ncv + 6 * ncv + 60;
    /* Allocate memory */
    if (!(comm = NAG_ALLOC(lcomm, double)) ||
        !(eigvr = NAG_ALLOC(ncv, double)) ||
        !(eigvi = NAG_ALLOC(ncv, double)) ||
        !(eigest = NAG_ALLOC(ncv, double)) ||
        !(dd = NAG_ALLOC(n, double)) ||
        !(dl = NAG_ALLOC(n, double)) ||
        !(du = NAG_ALLOC(n, double)) ||
        !(du2 = NAG_ALLOC(n, double)) ||
        !(resid = NAG_ALLOC(n, double)) ||
        !(v = NAG_ALLOC(n * ncv, double)) ||
        !(x2 = NAG_ALLOC(n, double)) ||
        !(icomm = NAG_ALLOC(licomm, Integer)) ||
        !(ipiv = NAG_ALLOC(n, Integer)))
    {
        printf("Allocation failure\n");
        exit_status = -1;
        goto END;
    }
    /* Initialize communication arrays for problem using
       nag_real_sparse_eigensystem_init (f12aac). */
    nag_real_sparse_eigensystem_init(n, nev, ncv, icomm, licomm, comm,
                                     lcomm, &fail);
    if (fail.code != NE_NOERROR) {
        printf("Error from nag_real_sparse_eigensystem_init (f12aac).\n%s\n",
               fail.message);
        exit_status = 1;
        goto END;
    }
    /* Select the required spectrum using

```

```

    nag_real_sparse_eigensystem_option (f12adc). */
nag_real_sparse_eigensystem_option("SHIFTED REAL", icomm, comm, &fail);
if (fail.code != NE_NOERROR) {
    printf("Error from nag_real_sparse_eigensystem_init (f12aac).\n%s\n",
        fail.message);
    exit_status = 1;
    goto END;
}
/* Select the problem type using
    nag_real_sparse_eigensystem_option (f12adc). */
nag_real_sparse_eigensystem_option("GENERALIZED", icomm, comm, &fail);
/* Construct C = A - SIGMA*I, and factor C using my_dgttrf. */
h = 1.0 / (double) (n + 1);
s = rho / 2.0;
s1 = -1.0 / h - s - sigmar * h / 6.0;
s2 = 2.0 / h - sigmar * 4.0 * h / 6.0;
s3 = -1.0 / h + s - sigmar * h / 6.0;
for (j = 0; j <= n - 2; ++j) {
    dl[j] = s1;
    dd[j] = s2;
    du[j] = s3;
}
dd[n - 1] = s2;

my_dgttrf(n, dl, dd, du, du2, ipiv, &info);

irevcm = 0;
REVCOMLOOP:
/* repeated calls to reverse communication routine
    nag_real_sparse_eigensystem_iter (f12abc). */
nag_real_sparse_eigensystem_iter(&irevcm, resid, v, &x, &y, &mx,
    &nshift, comm, icomm, &fail);
if (irevcm != 5) {
    if (irevcm == -1) {
        /* Perform y <--- OP*x = inv[A-SIGMA*M]*M*x using
            my_dggtrs */
        mv(n, x, x2);
        my_dgttrs(n, dl, dd, du, du2, ipiv, x2, y);
    }
    else if (irevcm == 1) {
        /* Perform y <--- OP*x = inv[A-SIGMA*M]*M*x where
            mx is available. */
        my_dgttrs(n, dl, dd, du, du2, ipiv, mx, y);
    }
    else if (irevcm == 2) {
        /* Perform y <--- M*x */
        mv(n, x, y);
    }
    else if (irevcm == 4 && imon == 1) {
        /* If imon=1, get monitoring information using
            nag_real_sparse_eigensystem_monit (f12aec). */
        nag_real_sparse_eigensystem_monit(&niter, &nconv, eigvr,
            eigvi, eigest, icomm, comm);
        /* Compute 2-norm of Ritz estimates using
            nag_dge_norm (f16rac). */
        nag_dge_norm(Nag_ColMajor, Nag_FrobeniusNorm, nev, 1, eigest,
            nev, &estnrm, &fail);
        printf("Iteration %3" NAG_IFMT " ", niter);
        printf(" No. converged = %3" NAG_IFMT " ", nconv);
        printf(" norm of estimates = %17.8e\n", estnrm);
    }
    goto REVCOMLOOP;
}
if (fail.code == NE_NOERROR) {
    /* Post-Process using nag_real_sparse_eigensystem_sol
        (f12acc) to compute eigenvalues/vectors. */
    nag_real_sparse_eigensystem_sol(&nconv, eigvr, eigvi, v, sigmar,
        sigmai, resid, v, comm, icomm, &fail);
    /* Print computed eigenvalues. */

    printf("\n The %4" NAG_IFMT " generalized Ritz values closest", nconv);
}

```

```

printf(" to unity are:\n\n");
for (j = 0; j <= nconv - 1; ++j) {
    printf("%8" NAG_IFMT "%5s( %12.4f ,%12.4f )\n", j + 1, "",
          sigmar + 1.0 / eigvr[j], eigvi[j]);
}
}
else {
    printf(" Error from nag_real_sparse_eigensystem_iter (f12abc).\n%s\n",
          fail.message);
    exit_status = 1;
    goto END;
}
}
END:
NAG_FREE(comm);
NAG_FREE(eigvr);
NAG_FREE(eigvi);
NAG_FREE(eigest);
NAG_FREE(dd);
NAG_FREE(dl);
NAG_FREE(du);
NAG_FREE(du2);
NAG_FREE(resid);
NAG_FREE(v);
NAG_FREE(icom);
NAG_FREE(ipiv);
NAG_FREE(x2);
return exit_status;
}

static void mv(Integer n, double *v, double *y)
{
    /* Compute the matrix vector multiplication Y<---M*X, where M is
       mass matrix formed by using piecewise linear elements on [0,1]. */

    /* Scalars */
    double h;
    Integer j;

    /* Function Body */
    h = 1.0 / (double) (6 * (n + 1));
    y[0] = h * (v[0] * 4.0 + v[1]);
    for (j = 1; j <= n - 2; ++j) {
        y[j] = h * (v[j - 1] + v[j] * 4.0 + v[j + 1]);
    }
    y[n - 1] = h * (v[n - 2] + v[n - 1] * 4.0);
    return;
} /* mv */

static void my_dgtrf(Integer n, double dl[], double d[],
                   double du[], double du2[], Integer ipiv[],
                   Integer *info)
{
    /* A simple C version of the Lapack routine dgtrf with argument
       checking removed */
    /* Scalars */
    double temp, fact;
    Integer i;
    /* Function Body */
    *info = 0;
    for (i = 0; i < n; ++i) {
        ipiv[i] = i;
    }
    for (i = 0; i < n - 2; ++i) {
        du2[i] = 0.0;
    }
    for (i = 0; i < n - 2; i++) {
        if (fabs(d[i]) >= fabs(dl[i])) {
            /* No row interchange required, eliminate dl[i]. */
            if (d[i] != 0.0) {
                fact = dl[i] / d[i];
                dl[i] = fact;
            }
        }
    }
}

```

```

        d[i + 1] = d[i + 1] - fact * du[i];
    }
}
else {
    /* Interchange rows I and I+1, eliminate dl[I] */
    fact = d[i] / dl[i];
    d[i] = dl[i];
    dl[i] = fact;
    temp = du[i];
    du[i] = d[i + 1];
    d[i + 1] = temp - fact * d[i + 1];
    du2[i] = du[i + 1];
    du[i + 1] = -fact * du[i + 1];
    ipiv[i] = i + 1;
}
}
if (n > 1) {
    i = n - 2;
    if (fabs(d[i]) >= fabs(dl[i])) {
        if (d[i] != 0.0) {
            fact = dl[i] / d[i];
            dl[i] = fact;
            d[i + 1] = d[i + 1] - fact * du[i];
        }
    }
    else {
        fact = d[i] / dl[i];
        d[i] = dl[i];
        dl[i] = fact;
        temp = du[i];
        du[i] = d[i + 1];
        d[i + 1] = temp - fact * d[i + 1];
        ipiv[i] = i + 1;
    }
}
/* Check for a zero on the diagonal of U. */
for (i = 0; i < n; ++i) {
    if (d[i] == 0.0) {
        *info = i;
        goto END;
    }
}
END:
return;
}

static void my_dgttrs(Integer n, double dl[], double d[],
                    double du[], double du2[], Integer ipiv[],
                    double b[], double y[])
{
    /* A simple C version of the Lapack routine dgttrs with argument
       checking removed, the number of right-hand-sides=1, Trans='N' */
    /* Scalars */
    Integer i, ip;
    double temp;
    /* Solve L*x = b. */
    for (i = 0; i <= n - 1; ++i) {
        y[i] = b[i];
    }
    for (i = 0; i < n - 1; ++i) {
        ip = ipiv[i];
        temp = y[i + 1 - ip + i] - dl[i] * y[ip];
        y[i] = y[ip];
        y[i + 1] = temp;
    }
    /* Solve U*x = b. */
    y[n - 1] = y[n - 1] / d[n - 1];
    if (n > 1) {
        y[n - 2] = (y[n - 2] - du[n - 2] * y[n - 1]) / d[n - 2];
    }
}

```

```

for (i = n - 3; i >= 0; --i) {
    y[i] = (y[i] - du[i] * y[i + 1] - du2[i] * y[i + 2]) / d[i];
}
return;
}

```

10.2 Program Data

nag_real_sparse_eigensystem_option (f12adc) Example Program Data
 10 4 10 10.0 1.0 0.0 : Values for nx, nev, ncv, rho, sigmar, sigmai

10.3 Program Results

nag_real_sparse_eigensystem_option (f12adc) Example Program Results

The 4 generalized Ritz values closest to unity are:

1	(1.0287	,	0.0000)
2	(1.0155	,	0.0000)
3	(1.0088	,	0.0000)
4	(1.0055	,	0.0000)

11 Optional Parameters

Several optional parameters for the computational functions nag_real_sparse_eigensystem_iter (f12abc) and nag_real_sparse_eigensystem_sol (f12acc) define choices in the problem specification or the algorithm logic. In order to reduce the number of formal arguments of nag_real_sparse_eigensystem_iter (f12abc) and nag_real_sparse_eigensystem_sol (f12acc) these optional parameters have associated *default values* that are appropriate for most problems. Therefore, you need only specify those optional parameters whose values are to be different from their default values.

The remainder of this section can be skipped if you wish to use the default values for all optional parameters.

The following is a list of the optional parameters available. A full description of each optional parameter is provided in Section 11.1.

Advisory

Defaults

Exact Shifts

Generalized

Initial Residual

Iteration Limit

Largest Imaginary

Largest Magnitude

Largest Real

List

Monitoring

Nolist

Print Level

Random Residual

Regular

Regular Inverse

Shifted Inverse Imaginary

Shifted Inverse Real

Smallest Imaginary

Smallest Magnitude

Smallest Real

Standard**Supplied Shifts****Tolerance****Vectors**

Optional parameters may be specified by calling `nag_real_sparse_eigensystem_option` (f12adc) before a call to `nag_real_sparse_eigensystem_iter` (f12abc), but after a call to `nag_real_sparse_eigensystem_init` (f12aac). One call is necessary for each optional parameter.

All optional parameters you do not specify are set to their default values. Optional parameters you specify are unaltered by `nag_real_sparse_eigensystem_iter` (f12abc) and `nag_real_sparse_eigensystem_sol` (f12acc) (unless they define invalid values) and so remain in effect for subsequent calls unless you alter them.

11.1 Description of the Optional Parameters

For each option, we give a summary line, a description of the optional parameter and details of constraints.

The summary line contains:

the keywords, where the minimum abbreviation of each keyword is underlined;

a parameter value, where the letters *a*, *i* and *r* denote options that take character, integer and real values respectively;

the default value, where the symbol ϵ is a generic notation for *machine precision* (see `nag_machine_precision` (X02AJC)).

Keywords and character values are case and white space insensitive.

Optional parameters used to specify files (e.g., **Advisory** and **Monitoring**) have type `Nag_FileID`. This ID value must either be set to 0 (the default value) in which case there will be no output, or will be as returned by a call of `nag_open_file` (x04acc).

Advisory

Default = 0

(See Section 2.3.1.1 in How to Use the NAG Library and its Documentation for further information on NAG data types.)

Advisory messages are output to `Nag_FileID Advisory` during the solution of the problem.

Defaults

This special keyword may be used to reset all optional parameters to their default values.

Exact Shifts

Default

Supplied Shifts

During the Arnoldi iterative process, shifts are applied internally as part of the implicit restarting scheme. The shift strategy used by default and selected by the **Exact Shifts** is strongly recommended over the alternative **Supplied Shifts** (see Lehoucq *et al.* (1998) for details of shift strategies).

If **Exact Shifts** are used then these are computed internally by the algorithm in the implicit restarting scheme.

If **Supplied Shifts** are used then, during the Arnoldi iterative process, you must supply shifts through array arguments of `nag_real_sparse_eigensystem_iter` (f12abc) when `nag_real_sparse_eigensystem_iter` (f12abc) returns with `irevcn` = 3; the real and imaginary parts of the shifts are supplied in `y` and `mx` respectively. This option should only be used if you are an experienced user since this requires some algorithmic knowledge and because more operations are usually required than for the implicit shift scheme. Details on the use of explicit shifts and further references on shift strategies are available in Lehoucq *et al.* (1998).

Iteration Limit *i* Default = 300

The limit on the number of Arnoldi iterations that can be performed before nag_real_sparse_eigen_system_iter (f12abc) exits. If not all requested eigenvalues have converged to within **Tolerance** and the number of Arnoldi iterations has reached this limit then nag_real_sparse_eigensystem_iter (f12abc) exits with an error; nag_real_sparse_eigensystem_sol (f12acc) can still be called subsequently to return the number of converged eigenvalues, the converged eigenvalues and, if requested, the corresponding eigenvectors.

Largest Magnitude Default

Largest Imaginary

Largest Real

Smallest Imaginary

Smallest Magnitude

Smallest Real

The Arnoldi iterative method converges on a number of eigenvalues with given properties. The default is for nag_real_sparse_eigensystem_iter (f12abc) to compute the eigenvalues of largest magnitude using **Largest Magnitude**. Alternatively, eigenvalues may be chosen which have **Largest Real** part, **Largest Imaginary** part, **Smallest Magnitude**, **Smallest Real** part or **Smallest Imaginary** part.

Note that these options select the eigenvalue properties for eigenvalues of OP (and B for **Generalized** problems), the linear operator determined by the computational mode and problem type.

Nolist Default

List

Normally each optional parameter specification is not printed to **Advisory** as it is supplied. Optional parameter **List** may be used to enable printing and optional parameter **Nolist** may be used to suppress the printing.

Monitoring Default = -1

(See Section 2.3.1.1 in How to Use the NAG Library and its Documentation for further information on NAG data types.)

Unless **Monitoring** is set to -1 (the default), monitoring information is output to Nag_FileID **Monitoring** during the solution of each problem; this may be the same as **Advisory**. The type of information produced is dependent on the value of **Print Level**, see the description of the optional parameter **Print Level** in this section for details of the information produced. Please see nag_open_file (x04acc) to associate a file with a given Nag_FileID.

Print Level *i* Default = 0

This controls the amount of printing produced by nag_real_sparse_eigensystem_option (f12adc) as follows.

- = 0 No output except error messages.
- > 0 The set of selected options.
- = 2 Problem and timing statistics on final exit from nag_real_sparse_eigensystem_iter (f12abc).
- ≥ 5 A single line of summary output at each Arnoldi iteration.
- ≥ 10 If **Monitoring** is set, then at each iteration, the length and additional steps of the current Arnoldi factorization and the number of converged Ritz values; during re-orthogonalization, the norm of initial/restarted starting vector.
- ≥ 20 Problem and timing statistics on final exit from nag_real_sparse_eigensystem_iter (f12abc). If **Monitoring** is set, then at each iteration, the number of shifts being applied, the eigenvalues and estimates of the Hessenberg matrix H , the size of the Arnoldi basis, the wanted Ritz values and associated Ritz estimates and the shifts applied; vector norms prior to and following re-orthogonalization.

- ≥ 30 If **Monitoring** is set, then on final iteration, the norm of the residual; when computing the Schur form, the eigenvalues and Ritz estimates both before and after sorting; for each iteration, the norm of residual for compressed factorization and the compressed upper Hessenberg matrix H ; during re-orthogonalization, the initial/restarted starting vector; during the Arnoldi iteration loop, a restart is flagged and the number of the residual requiring iterative refinement; while applying shifts, the indices of the shifts being applied.
- ≥ 40 If **Monitoring** is set, then during the Arnoldi iteration loop, the Arnoldi vector number and norm of the current residual; while applying shifts, key measures of progress and the order of H ; while computing eigenvalues of H , the last rows of the Schur and eigenvector matrices; when computing implicit shifts, the eigenvalues and Ritz estimates of H .
- ≥ 50 If **Monitoring** is set, then during Arnoldi iteration loop: norms of key components and the active column of H , norms of residuals during iterative refinement, the final upper Hessenberg matrix H ; while applying shifts: number of shifts, shift values, block indices, updated matrix H ; while computing eigenvalues of H : the matrix H , the computed eigenvalues and Ritz estimates.

Random Residual

Default

Initial Residual

To begin the Arnoldi iterative process, nag_real_sparse_eigensystem_iter (f12abc) requires an initial residual vector. By default nag_real_sparse_eigensystem_iter (f12abc) provides its own random initial residual vector; this option can also be set using optional parameter **Random Residual**. Alternatively, you can supply an initial residual vector (perhaps from a previous computation) to nag_real_sparse_eigensystem_iter (f12abc) through the array argument **resid**; this option can be set using optional parameter **Initial Residual**.

Regular

Default

Regular Inverse**Shifted Inverse Imaginary****Shifted Inverse Real**

These options define the computational mode which in turn defines the form of operation $OP(x)$ to be performed when nag_real_sparse_eigensystem_iter (f12abc) returns with **irevcm** = -1 or 1 and the matrix-vector product Bx when nag_real_sparse_eigensystem_iter (f12abc) returns with **irevcm** = 2.

Given a **Standard** eigenvalue problem in the form $Ax = \lambda x$ then the following modes are available with the appropriate operator $OP(x)$.

Regular

$$OP = A$$

Shifted Inverse Real

$$OP = (A - \sigma I)^{-1} \text{ where } \sigma \text{ is real}$$

Given a **Generalized** eigenvalue problem in the form $Ax = \lambda Bx$ then the following modes are available with the appropriate operator $OP(x)$.

Regular Inverse

$$OP = B^{-1}A$$

Shifted Inverse Real with real shift

$$OP = (A - \sigma B)^{-1}B, \text{ where } \sigma \text{ is real}$$

Shifted Inverse Real with complex shift

$$OP = \text{Real}\left((A - \sigma B)^{-1}B\right), \text{ where } \sigma \text{ is complex}$$

Shifted Inverse Imaginary

$$OP = \text{Imag}\left((A - \sigma B)^{-1}B\right), \text{ where } \sigma \text{ is complex}$$

Standard

Default

Generalized

The problem to be solved is either a standard eigenvalue problem, $Ax = \lambda x$, or a generalized eigenvalue problem, $Ax = \lambda Bx$. The optional parameter **Standard** should be used when a standard eigenvalue problem is being solved and the optional parameter **Generalized** should be used when a generalized eigenvalue problem is being solved.

Tolerance r Default = ϵ

An approximate eigenvalue has deemed to have converged when the corresponding Ritz estimate is within **Tolerance** relative to the magnitude of the eigenvalue.

Vectors

Default = RITZ

The function `nag_real_sparse_eigensystem_sol` (f12acc) can optionally compute the Schur vectors and/or the eigenvectors corresponding to the converged eigenvalues. To turn off computation of any vectors the option **Vectors** = NONE should be set. To compute only the Schur vectors (at very little extra cost), the option **Vectors** = SCHUR should be set and these will be returned in the array argument **v** of `nag_real_sparse_eigensystem_sol` (f12acc). To compute the eigenvectors (Ritz vectors) corresponding to the eigenvalue estimates, the option **Vectors** = RITZ should be set and these will be returned in the array argument **z** of `nag_real_sparse_eigensystem_sol` (f12acc), if **z** is set equal to **v** (as in Section 10) then the Schur vectors in **v** are overwritten by the eigenvectors computed by `nag_real_sparse_eigensystem_sol` (f12acc).
