X04BHFP

NAG Parallel Library Routine Document

Note: before using this routine, please read the Users' Note for your implementation to check for implementation-dependent details. You are advised to enclose any calls to NAG Parallel Library routines between calls to Z01AAFP and Z01ABFP.

1 Description

X04BHFP outputs an m by n real matrix A stored in a cyclic two-dimensional block distribution on a logical grid of processors to an external file (in its natural, non-distributed form).

This routine outputs matrices stored in the form required by some routines in Chapter F04.

2 Specification

```
SUBROUTINE X04BHFP(ICNTXT, NOUT, M, N, NB, A, LDA, FORMAT, WORK,1IFAIL)DOUBLE PRECISIONA(LDA,*), WORK(*)INTEGERICNTXT, NOUT, M, N, NB, LDA, IFAILCHARACTER*(*)FORMAT
```

3 Usage

3.1 Definitions

The following definitions are used in describing the data distribution within this document:

m_p	_	the number of rows in the Library Grid.	
n_p	_	the number of columns in the Library Grid.	
p_r	_	the row grid coordinate of the calling processor.	
p_c	_	the column grid coordinate of the calling processor.	
N_b	_	the blocking factor for the distribution of the rows and columns of a	
		matrix X .	
$\operatorname{numroc}(\alpha, b_\ell, q, s, k)$	_	a function which gives the num ber of rows or columns of a distributed matrix owned by the processor with the row or column coordinate q (p_r or p_c), where α is the total number of rows or columns of the matrix, b_ℓ is the blocking factor used (N_b), s is the row or column coordinate of the processor that possesses the first row or column of the distributed matrix and k is either n_p or m_p . The Library provides the function Z01CAFP (NUMROC) for the evaluation of this function.	

3.2 Global and Local Arguments

The following global **input** arguments must have the same value on entry to the routine on each processor and the global **output** arguments will have the same value on exit from the routine on each processor:

Global input arguments: M, N, NB, IFAIL Global output arguments: IFAIL

Note: NOUT and FORMAT are only referenced on the root (or $\{0,0\}$) processor since it is only the root (or $\{0,0\}$ processor) which performs output.

3.3 Distribution Strategy

The matrix A should be partitioned into N_b by N_b square blocks and stored in an array A in a cyclic two-dimensional block distribution. This data distribution is described in more detail in the Essential Introduction of the NAG Parallel Library and in the F04 Chapter Introduction.

This routine assumes that the data has already been correctly distributed, and if this is not the case will fail to produce correct results.

4 Arguments

1:	ICNTXT — INTEGER	Local Input	
	<i>On entry:</i> the Library context, usually returned by a call to the Library Z01AAFP.	Grid initialisation routine	
	Note: the value of ICNTXT must not be changed.		
2:	NOUT — INTEGER	Local Input	
	On entry: the unit number to which the output will be directed.		
	Constraint: $0 \leq \text{NOUT} \leq 99$.		
3:	M — INTEGER	Global Input	
	On entry: m , the number of rows of the matrix A .		
	Constraint: $M \ge 0$.		
4:	N — INTEGER	Global Input	
	On entry: n , the number of columns of the matrix A .	-	
	Constraint: $N \ge 0$.		
5:	NB — INTEGER	Global Input	
	On entry: N_b , the blocking factor for distributing the matrix A.		
	Constraint: $NB \ge 1$.		
6:	A(LDA,*) — DOUBLE PRECISION array	Local Input	
	Note: the size of the second dimension of the array A must be at least	-	
	$\max(1, \operatorname{numroc}(N, \operatorname{NB}, p_c, 0, n_p)).$		
	On entry: the local part of the matrix A, distributed in a cyclic two-dim	mensional block fashion.	
7:	LDA - INTEGER	Local Input	
	On entry: the dimension of the array A as declared in the (sub)program called.	n from which X04BHFP is	
	Constraint: LDA $\geq \max(1, \operatorname{numroc}(M, \operatorname{NB}, p_r, 0, m_p)).$		
8:	$FORMAT - CHARACTER^*(*)$	Local Input	
	On entry: the format which will be used for output of the elements of A	Α.	
	Constraint: any legal Fortran format for the output of floating-point nu	imbers.	
9:	WORK(*) — DOUBLE PRECISION array	Local Workspace	
	Note: the dimension of the array WORK must be at least $\max(1,N)$.	-	
10:	IFAIL — INTEGER	Global Input/Global Output	
	The NAG Parallel Library provides a mechanism, via the routine Z02EAFP, to reduce the amount of parameter validation performed by this routine. For a full description refer to the Z02 Chapter Introduction.		
	On entry: IFAIL must be set to $0, -1$ or 1 . For users not familiar with t the Essential Introduction) the recommended values are:	his argument (described in	
	IFAIL = 0, if multigridding is not employed; IFAIL = -1 , if multigridding is employed.		

On exit: IFAIL = 0 (or -9999 if reduced error checking is enabled) unless the routine detects an error (see Section 5).

5 Errors and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output from the root processor (or processor $\{0,0\}$ when the root processor is not available) on the current error message unit (as defined by X04AAF).

5.1 Full Error Checking Mode Only

IFAIL = -2000

The routine has been called with an invalid value of ICNTXT on one or more processors.

IFAIL = -1000

The logical processor grid and library mechanism (Library Grid) have not been correctly defined, see Z01AAFP.

IFAIL = -i

On entry, the *i*th argument was invalid. This error occured either because a global argument did not have the same value on all logical processors, or because its value on one or more processors was incorrect. An explanatory message distinguishes between these two cases.

5.2 Any Error Checking Mode

IFAIL = 1

An error has occurred in writing to unit NOUT. The file may already have been opened for reading only or the user may have run out of disk space.

6 Further Comments

Output is performed by the root (or $\{0,0\}$) processor if the root processor is not available. All other processors communicate their local portion of the matrix to the root (or $\{0,0\}$) processor.

7 References

None.

8 Example

See Section 8 of the document for X04BGFP.