NAG Library Routine Document

G02HMF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

G02HMF computes a robust estimate of the covariance matrix for user-supplied weight functions. The derivatives of the weight functions are not required.

2 Specification

3 Description

For a set of n observations on m variables in a matrix X, a robust estimate of the covariance matrix, C, and a robust estimate of location, θ , are given by

$$C = \tau^2 \left(A^{\mathsf{T}} A \right)^{-1},$$

where τ^2 is a correction factor and A is a lower triangular matrix found as the solution to the following equations.

$$z_i = A(x_i - \theta)$$

$$\frac{1}{n} \sum_{i=1}^{n} w(\|z_i\|_2) z_i = 0$$

and

$$\frac{1}{n} \sum_{i=1}^{n} u \big(\|z_i\|_2 \big) z_i z_i^{\mathsf{T}} - v \big(\|z_i\|_2 \big) I = 0,$$

where x_i is a vector of length m containing the elements of the ith row of X,

 z_i is a vector of length m,

I is the identity matrix and 0 is the zero matrix.

and w and u are suitable functions.

G02HMF covers two situations:

- (i) v(t) = 1 for all t,
- (ii) v(t) = u(t).

The robust covariance matrix may be calculated from a weighted sum of squares and cross-products matrix about θ using weights $wt_i = u(||z_i||)$. In case (i) a divisor of n is used and in case (ii) a divisor of

Mark 25 G02HMF.1

 $\sum_{i=1}^{n} wt_i$ is used. If $w(.) = \sqrt{u(.)}$, then the robust covariance matrix can be calculated by scaling each row of X by $\sqrt{wt_i}$ and calculating an unweighted covariance matrix about θ .

In order to make the estimate asymptotically unbiased under a Normal model a correction factor, τ^2 , is needed. The value of the correction factor will depend on the functions employed (see Huber (1981) and Marazzi (1987)).

G02HMF finds A using the iterative procedure as given by Huber; see Huber (1981).

$$A_k = (S_k + I)A_{k-1}$$

and

$$\theta_{j_k} = \frac{b_j}{D_1} + \theta_{j_{k-1}},$$

where $S_k = (s_{jl})$, for j = 1, 2, ..., m and l = 1, 2, ..., m is a lower triangular matrix such that

$$s_{jl} = \begin{cases} -\min[\max(h_{jl}/D_2, -BL), BL], & j > l \\ -\min[\max(\frac{1}{2}(h_{jj}/D_2 - 1), -BD), BD], & j = l \end{cases},$$

where

$$D_{1} = \sum_{i=1}^{n} w(\|z_{i}\|_{2})$$

$$D_{2} = \sum_{i=1}^{n} u(\|z_{i}\|_{2})$$

$$h_{jl} = \sum_{i=1}^{n} u(\|z_{i}\|_{2}) z_{ij} z_{il}, \text{ for } j \geq l$$

$$b_{j} = \sum_{i=1}^{n} w(\|z_{i}\|_{2}) (x_{ij} - b_{j})$$

and BD and BL are suitable bounds.

The value of τ may be chosen so that C is unbiased if the observations are from a given distribution. G02HMF is based on routines in ROBETH; see Marazzi (1987).

4 References

Huber P J (1981) Robust Statistics Wiley

Marazzi A (1987) Weights for bounded influence regression in ROBETH Cah. Rech. Doc. IUMSP, No. 3 ROB 3 Institut Universitaire de Médecine Sociale et Préventive, Lausanne

5 Parameters

1: UCV - SUBROUTINE, supplied by the user. External Procedure UCV must return the values of the functions u and w for a given value of its argument.

```
The specification of UCV is:

SUBROUTINE UCV (T, RUSER, U, W)

REAL (KIND=nag_wp) T, RUSER(*), U, W
```

G02HMF.2 Mark 25

1: T - REAL (KIND=nag_wp)

Input

On entry: the argument for which the functions u and w must be evaluated.

2: RUSER(*) - REAL (KIND=nag_wp) array

User Workspace

UCV is called with the parameter RUSER as supplied to G02HMF. You are free to use the array RUSER to supply information to UCV as an alternative to using COMMON global variables.

3: $U - REAL (KIND=nag_wp)$

Output

On exit: the value of the u function at the point T.

 $\textit{Constraint} : \ U \geq 0.0.$

4: W - REAL (KIND=nag wp)

Output

On exit: the value of the w function at the point T.

Constraint: $W \ge 0.0$.

UCV must either be a module subprogram USEd by, or declared as EXTERNAL in, the (sub)program from which G02HMF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

2: RUSER(*) - REAL (KIND=nag_wp) array

User Workspace

RUSER is not used by G02HMF, but is passed directly to UCV and may be used to pass information to this routine as an alternative to using COMMON global variables.

3: INDM - INTEGER

Input

On entry: indicates which form of the function v will be used.

INDM = 1

v = 1.

 $\text{INDM} \neq 1$

v = u.

4: N – INTEGER

Input

On entry: n, the number of observations.

Constraint: N > 1.

5: M – INTEGER

Input

On entry: m, the number of columns of the matrix X, i.e., number of independent variables.

Constraint: $1 \le M \le N$.

6: $X(LDX, M) - REAL (KIND=nag_wp)$ array

Input

On entry: X(i,j) must contain the *i*th observation on the *j*th variable, for $i=1,2,\ldots,n$ and $j=1,2,\ldots,m$.

7: LDX – INTEGER

Input

On entry: the first dimension of the array X as declared in the (sub)program from which G02HMF is called.

Constraint: $LDX \ge N$.

Mark 25 G02HMF.3

8: $COV(M \times (M+1)/2) - REAL$ (KIND=nag wp) array

Output

On exit: a robust estimate of the covariance matrix, C. The upper triangular part of the matrix C is stored packed by columns (lower triangular stored by rows), that is C_{ij} is returned in $COV(j \times (j-1)/2 + i)$, $i \le j$.

9: $A(M \times (M+1)/2) - REAL (KIND=nag_wp) array$

Input/Output

On entry: an initial estimate of the lower triangular real matrix A. Only the lower triangular elements must be given and these should be stored row-wise in the array.

The diagonal elements must be $\neq 0$, and in practice will usually be > 0. If the magnitudes of the columns of X are of the same order, the identity matrix will often provide a suitable initial value for A. If the columns of X are of different magnitudes, the diagonal elements of the initial value of A should be approximately inversely proportional to the magnitude of the columns of X.

Constraint: $A(j \times (j-1)/2 + j) \neq 0.0$, for j = 1, 2, ..., m.

On exit: the lower triangular elements of the inverse of the matrix A, stored row-wise.

10: $WT(N) - REAL (KIND=nag_wp) array$

Output

On exit: WT(i) contains the weights, $wt_i = u(||z_i||_2)$, for i = 1, 2, ..., n.

11: THETA(M) - REAL (KIND=nag_wp) array

Input/Output

On entry: an initial estimate of the location parameter, θ_i , for i = 1, 2, ..., m.

In many cases an initial estimate of $\theta_j = 0$, for j = 1, 2, ..., m, will be adequate. Alternatively medians may be used as given by G07DAF.

On exit: contains the robust estimate of the location parameter, θ_j , for $j=1,2,\ldots,m$.

12: BL – REAL (KIND=nag wp)

Input

On entry: the magnitude of the bound for the off-diagonal elements of S_k , BL.

Suggested value: BL = 0.9.

Constraint: BL > 0.0.

13: BD - REAL (KIND=nag wp)

Input

On entry: the magnitude of the bound for the diagonal elements of S_k , BD.

Suggested value: BD = 0.9.

Constraint: BD > 0.0.

14: MAXIT – INTEGER

Input

On entry: the maximum number of iterations that will be used during the calculation of A.

Suggested value: MAXIT = 150.

Constraint: MAXIT > 0.

15: NITMON - INTEGER

Input

On entry: indicates the amount of information on the iteration that is printed.

NITMON > 0

The value of A, θ and δ (see Section 7) will be printed at the first and every NITMON iterations.

NITMON < 0

No iteration monitoring is printed.

G02HMF.4 Mark 25

When printing occurs the output is directed to the current advisory message channel (See X04ABF.)

16: TOL – REAL (KIND=nag wp)

Input

On entry: the relative precision for the final estimate of the covariance matrix. Iteration will stop when maximum δ (see Section 7) is less than TOL.

Constraint: TOL > 0.0.

17: NIT - INTEGER

Output

On exit: the number of iterations performed.

18:
$$WK(2 \times M) - REAL (KIND=nag_wp) array$$

Workspace

19: IFAIL - INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
IFAIL = 1
```

```
\begin{array}{lll} \text{On entry, } N \leq 1, \\ \text{or} & M < 1, \\ \text{or} & N < M, \\ \text{or} & LDX < N. \end{array}
```

$\mathrm{IFAIL} = 2$

```
\begin{array}{lll} \text{On entry, } TOL \leq 0.0, \\ \text{or} & \text{MAXIT} \leq 0, \\ \text{or} & \text{diagonal element of } A = 0.0, \\ \text{or} & \text{BL} \leq 0.0, \\ \text{or} & \text{BD} \leq 0.0. \end{array}
```

IFAIL = 3

A column of X has a constant value.

IFAIL = 4

Value of U or W returned by UCV < 0.

IFAIL = 5

The routine has failed to converge in MAXIT iterations.

Mark 25 G02HMF.5

IFAIL = 6

Either the sum D_1 or the sum D_2 is zero. This may be caused by the functions u or w being too strict for the current estimate of A (or C). You should either try a larger initial estimate of A or make the u and w functions less strict.

IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.

See Section 3.8 in the Essential Introduction for further information.

IFAIL = -399

Your licence key may have expired or may not have been installed correctly.

See Section 3.7 in the Essential Introduction for further information.

IFAIL = -999

Dynamic memory allocation failed.

See Section 3.6 in the Essential Introduction for further information.

7 Accuracy

On successful exit the accuracy of the results is related to the value of TOL; see Section 5. At an iteration let

- (i) d1 = the maximum value of $|s_{il}|$
- (ii) d2 = the maximum absolute change in wt(i)
- (iii) d3 = the maximum absolute relative change in θ_i

and let $\delta = \max(d1, d2, d3)$. Then the iterative procedure is assumed to have converged when $\delta < \text{TOL}$.

8 Parallelism and Performance

G02HMF is not threaded by NAG in any implementation.

G02HMF makes calls to BLAS and/or LAPACK routines, which may be threaded within the vendor library used by this implementation. Consult the documentation for the vendor library for further information.

Please consult the X06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this routine. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

9 Further Comments

The existence of A will depend upon the function u (see Marazzi (1987)); also if X is not of full rank a value of A will not be found. If the columns of X are almost linearly related, then convergence will be slow.

If derivatives of the u and w functions are available then the method used in G02HLF will usually give much faster convergence.

10 Example

A sample of 10 observations on three variables is read in along with initial values for A and θ and parameter values for the u and w functions, c_u and c_w . The covariance matrix computed by G02HMF is printed along with the robust estimate of θ .

G02HMF.6 Mark 25

UCV computes the Huber's weight functions:

$$u(t) = 1$$
, if $t \le c_u^2$
 $u(t) = \frac{c_u}{t^2}$, if $t > c_u^2$

and

$$w(t) = 1,$$
 if $t \le c_w$
 $w(t) = \frac{c_w}{t},$ if $t > c_w$.

10.1 Program Text

```
GO2HMF Example Program Text
    Mark 25 Release. NAG Copyright 2014.
    Module g02hmfe_mod
!
      GO2HMF Example Program Module:
!
             Parameters and User-defined Routines
!
      .. Use Statements ..
     Use nag_library, Only: nag_wp
      .. Implicit None Statement ..
      Implicit None
      .. Accessibility Statements ..
      Private
      Public
                                            :: ucv
!
      .. Parameters ..
     Integer, Parameter, Public
                                        :: iset = 1, nin = 5, nout = 6
    Contains
     Subroutine ucv(t,ruser,u,w)
1
        u function
        .. Scalar Arguments ..
!
        Real (Kind=nag_wp), Intent (In)
Real (Kind=nag_wp), Intent (Out)
                                             :: t
                                              :: u, w
        .. Array Arguments ..
!
       Real (Kind=nag_wp), Intent (Inout) :: ruser(*)
!
        .. Local Scalars ..
        Real (Kind=nag_wp)
                                               :: cu, cw, t2
!
        .. Executable Statements ..
        cu = ruser(1)
        u = 1.0_nag_wp
        If (t/=0.0_nag_wp) Then
          t2 = t*t
          If (t2>cu) Then
            u = cu/t2
          End If
        End If
        w function
        cw = ruser(2)
        If (t>cw) Then
          w = cw/t
        Else
          w = 1.0_nag_wp
        End If
      End Subroutine ucv
    End Module g02hmfe_mod
    Program g02hmfe
      GO2HMF Example Main Program
!
      .. Use Statements ..
      Use nag_library, Only: g02hmf, nag_wp, x04abf, x04ccf
```

Mark 25 G02HMF.7

Use g02hmfe_mod, Only: iset, nin, nout, ucv

```
.. Implicit None Statement ..
     Implicit None
!
      .. Local Scalars ..
      Real (Kind=nag_wp)
                                            :: bd, bl, tol
                                            :: i, ifail, indm, la, lcov, ldx,
     Integer
                                               lruser, m, maxit, n, nadv, nit, &
                                               nitmon
      .. Local Arrays ..
     Real (Kind=nag_wp), Allocatable
                                           :: a(:), cov(:), ruser(:),
                                               theta(:), wk(:), wt(:), x(:,:)
!
      .. Executable Statements ..
     Write (nout,*) 'GO2HMF Example Program Results'
     Write (nout,*)
     Skip heading in data file
     Read (nin,*)
     Read in the problem size
!
     Read (nin,*) n, m
     ldx = n
      lruser = 2
      la = ((m+1)*m)/2
      lcov = la
     Allocate (x(ldx,m),ruser(lruser),cov(lcov),a(la),wt(n),theta(m),wk(2*m))
!
     Read in data
     Read (nin,*)(x(i,1:m),i=1,n)
     Read in the initial value of \mbox{\bf A}
     Read (nin,*) a(1:la)
     Read in the initial value of THETA
     Read (nin,*) theta(1:m)
     Read in the values of the parameters of the ucv functions
     Read (nin,*) ruser(1:lruser)
     Read in the control parameters
     Read (nin,*) indm, nitmon, bl, bd, maxit, tol
     Set the advisory channel to NOUT for monitoring information
!
      If (nitmon/=0) Then
       nadv = nout
       Call x04abf(iset,nadv)
     End If
     Compute robust estimate of variance / covariance matrix
      ifail = 0
      Call g02hmf(ucv,ruser,indm,n,m,x,ldx,cov,a,wt,theta,bl,bd,maxit,nitmon, &
       tol, nit, wk, ifail)
     Display results
     Write (nout,99999) 'GO2HMF required ', nit, ' iterations to converge'
     Write (nout,*)
     Flush (nout)
      ifail = 0
      Call x04ccf('Upper','Non-Unit',m,cov,'Robust covariance matrix',ifail)
     Write (nout,*)
     Write (nout,*) 'Robust estimates of THETA'
     Write (nout, 99998) theta(1:m)
99999 Format (1X,A,IO,A)
99998 Format (1X,F10.3)
   End Program g02hmfe
```

G02HMF.8 Mark 25

10.2 Program Data

10.3 Program Results

14.704

Mark 25 G02HMF.9 (last)