

NAG Library Function Document

nag_opt_sparse_convex_qp_option_set_integer (e04ntc)

1 Purpose

nag_opt_sparse_convex_qp_option_set_integer (e04ntc) may be used to supply individual Integer optional parameters to nag_opt_sparse_convex_qp_solve (e04nqc). The initialization function nag_opt_sparse_convex_qp_init (e04npc) **must** have been called before calling nag_opt_sparse_convex_qp_option_set_integer (e04ntc).

2 Specification

```
#include <nag.h>
#include <nage04.h>

void nag_opt_sparse_convex_qp_option_set_integer (const char *string,
        Integer ivalue, Nag_E04State *state, NagError *fail)
```

3 Description

nag_opt_sparse_convex_qp_option_set_integer (e04ntc) may be used to supply values for Integer optional parameters to nag_opt_sparse_convex_qp_solve (e04nqc). It is only necessary to call nag_opt_sparse_convex_qp_option_set_integer (e04ntc) for those arguments whose values are to be different from their default values. One call to nag_opt_sparse_convex_qp_option_set_integer (e04ntc) sets one argument value.

Each Integer optional parameter is defined by a single character string in **string** and the corresponding value in **ivalue**. For example, the following allows the iteration limit to be defined:

```
itnlim = 1000;
if (m > 500) itnlim = 500;
e04ntc ("Iterations", itnlim, &state, &fail);
```

Optional parameter settings are preserved following a call to nag_opt_sparse_convex_qp_solve (e04nqc) and so the keyword **Defaults** is provided to allow you to reset all the optional parameters to their default values before a subsequent call to nag_opt_sparse_convex_qp_solve (e04nqc).

A complete list of optional parameters, their abbreviations, synonyms and default values is given in Section 12 in nag_opt_sparse_convex_qp_solve (e04nqc).

4 References

None.

5 Arguments

- 1: **string** – const char * *Input*
On entry: a single valid keyword of an Integer optional parameter (as described in Section 12 in nag_opt_sparse_convex_qp_solve (e04nqc)).
- 2: **ivalue** – Integer *Input*
On entry: an Integer value associated with the keyword in **string**.
- 3: **state** – Nag_E04State * *Communication Structure*
state contains internal information required for functions in this suite. It must not be modified in any way.

- 4: **fail** – NagError * *Input/Output*
 The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.
 See Section 2.3.1.2 in How to Use the NAG Library and its Documentation for further information.

NE_BAD_PARAM

On entry, argument $\langle value \rangle$ had an illegal value.

NE_E04_OPTION_INVALID

The supplied option is invalid. Check that the keywords are neither ambiguous nor misspelt. The option string is ' $\langle value \rangle$ ' and **ivalue** = $\langle value \rangle$.

NE_E04NPC_NOT_INIT

The initialization function `nag_opt_sparse_convex_qp_init (e04npc)` has not been called.

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please contact NAG for assistance.

An unexpected error has been triggered by this function. Please contact NAG.
 See Section 2.7.6 in How to Use the NAG Library and its Documentation for further information.

NE_NO_LICENCE

Your licence key may have expired or may not have been installed correctly.
 See Section 2.7.5 in How to Use the NAG Library and its Documentation for further information.

7 Accuracy

Not applicable.

8 Parallelism and Performance

`nag_opt_sparse_convex_qp_option_set_integer (e04ntc)` is not threaded in any implementation.

9 Further Comments

`nag_opt_sparse_convex_qp_option_set_file (e04nrc)` or `nag_opt_sparse_convex_qp_option_set_string (e04nsc)` may also be used to supply Integer optional parameters to `nag_opt_sparse_convex_qp_solve (e04nqc)`.

10 Example

See Section 10 in `nag_opt_sparse_convex_qp_solve (e04nqc)` and `nag_opt_sparse_convex_qp_option_set_file (e04nrc)`.
