

NAG Library Function Document

nag_code_to_error_name (x04ndc)

1 Purpose

`nag_code_to_error_name (x04ndc)` converts an integer error code to its corresponding string error name. The integer error code is typically returned as part of the NAG error structure by a prior call to a NAG C Library function.

2 Specification

```
#include <nag.h>
#include <nagx04.h>
const char * nag_code_to_error_name (int code)
```

3 Description

`nag_code_to_error_name (x04ndc)` takes as input the value of the integer error code returned in the NAG error structure and returns the corresponding string error name. This can be useful when you want to print the returned error code as a name. For example the **NE_BAD_PARAM** code has the value 70. A call to `nag_code_to_error_name (x04ndc)(70)` returns the string ‘**NE_BAD_PARAM**’.

`nag_code_to_error_name (x04ndc)` returns 0 (null pointer) if the input value is not recognized as a valid NAG error code.

4 References

None.

5 Arguments

1: code – int	<i>Input</i>
----------------------	--------------

On entry: the value of a NAG error code.

6 Error Indicators and Warnings

7 Accuracy

Not applicable.

8 Parallelism and Performance

`nag_code_to_error_name (x04ndc)` is not threaded in any implementation.

9 Further Comments

None.

10 Example

This example produces error name strings corresponding to a number of integer error codes.

10.1 Program Text

```
/* nag_code_to_error_name (x04ndc) Example Program.
*
* NAGPRODCODE Version.
*
* Copyright 2016 Numerical Algorithms Group.
*
* Mark 26, 2016.
*/
#include <stdio.h>
#include <nag.h>
#include <nag_stdl�.h>
#include <nag_string.h>
#include <nagx04.h>

int main(void)
{
    /* Scalars */
    Integer exit_status = 0;
    unsigned i;
    /* Pointers */
    const char *str_error = 0;

    int fail_code[] = { NE_BAD_PARAM, NE_INCOMPAT_PARAM, NE_COMPLEX_ZERO,
        NE_NOT_MONOTONIC, NE_TOO_MANY_ITER, NE_SINGULAR,
        NE_INITIALIZATION
    };

    printf("nag_code_to_error_name (x04ndc) Example Program Results\n\n");

    /* Print header. */
    printf("    Code value          Error name\n");
    printf("    -----          -----\\n");

    /* Convert the error code to strings and print. */

    /* nag_code_to_error_name (x04ndc).
     * Converts NAG error code to its string value
     */
    for (i = 0; i < sizeof(fail_code) / sizeof(int); i++) {
        str_error = nag_code_to_error_name(fail_code[i]);
        if (str_error)
            printf("%-7d      %-s\\n", fail_code[i], str_error);
        else {
            exit_status = 1;
            goto END;
        }
    }
END:
    return exit_status;
}
```

10.2 Program Data

None.

10.3 Program Results

nag_code_to_error_name (x04ndc) Example Program Results

Code value	Error name
70	NE_BAD_PARAM
88	NE_INCOMPAT_PARAM
133	NE_COMPLEX_ZERO
245	NE_NOT_MONOTONIC
357	NE_TOO_MANY_ITER
366	NE_SINGULAR
2049	NE_INITIALIZATION
