

NAG Library Function Document

nag_sparse_nherm_basic_diagnostic (f11btc)

1 Purpose

nag_sparse_nherm_basic_diagnostic (f11btc) is the third in a suite of three functions for the iterative solution of a complex general (non-Hermitian) system of simultaneous linear equations (see Golub and Van Loan (1996)). nag_sparse_nherm_basic_diagnostic (f11btc) returns information about the computations during an iteration and/or after this has been completed. The first function of the suite, nag_sparse_nherm_basic_setup (f11brc), is a setup function; the second function, nag_sparse_nherm_basic_solver (f11bsc), is the iterative solver itself.

These three functions are suitable for the solution of large sparse general (non-Hermitian) systems of equations.

2 Specification

```
#include <nag.h>
#include <nagf11.h>

void nag_sparse_nherm_basic_diagnostic (Integer *itn, double *stplhs,
    double *stprhs, double *anorm, double *sigmax, Complex work[],
    Integer lwork, NagError *fail)
```

3 Description

nag_sparse_nherm_basic_diagnostic (f11btc) returns information about the solution process. It can be called either during a monitoring step of nag_sparse_nherm_basic_solver (f11bsc) or after nag_sparse_nherm_basic_solver (f11bsc) has completed its tasks. Calling nag_sparse_nherm_basic_diagnostic (f11btc) at any other time will result in an error condition being raised.

For further information you should read the documentation for nag_sparse_nherm_basic_setup (f11brc) and nag_sparse_nherm_basic_solver (f11bsc).

4 References

Golub G H and Van Loan C F (1996) *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

5 Arguments

- 1: **itn** – Integer * *Output*
On exit: the number of iterations carried out by nag_sparse_nherm_basic_solver (f11bsc).
- 2: **stplhs** – double * *Output*
On exit: the current value of the left-hand side of the termination criterion used by nag_sparse_nherm_basic_solver (f11bsc).
- 3: **stprhs** – double * *Output*
On exit: the current value of the right-hand side of the termination criterion used by nag_sparse_nherm_basic_solver (f11bsc).

- 4: **anorm** – double * *Output*
On exit: if **iterm** = 1 in the previous call to `nag_sparse_nherm_basic_setup` (f11brc), then **anorm** contains $\|A\|_p$, where $p = 1, 2$ or ∞ , either supplied or, in the case of 1 or ∞ , estimated by `nag_sparse_nherm_basic_solver` (f11bsc); otherwise **anorm** = 0.0.
- 5: **sigmax** – double * *Output*
On exit: if **iterm** = 2 in the previous call to `nag_sparse_nherm_basic_setup` (f11brc), the current estimate of the largest singular value $\sigma_1(\bar{A})$ of the preconditioned iteration matrix when it is used by the termination criterion in `nag_sparse_nherm_basic_solver` (f11bsc), either when it has been supplied to `nag_sparse_nherm_basic_setup` (f11brc) or it has been estimated by `nag_sparse_nherm_basic_solver` (f11bsc) (see also Sections 3 and 5 in `nag_sparse_nherm_basic_setup` (f11brc)); otherwise, **sigmax** = 0.0 is returned.
- 6: **work[lwork]** – Complex *Communication Array*
On entry: the array **work** as returned by `nag_sparse_nherm_basic_solver` (f11bsc) (see also Sections 3 and 5 in `nag_sparse_nherm_basic_solver` (f11bsc)).
- 7: **lwork** – Integer *Input*
On entry: the dimension of the array **work** (see also `nag_sparse_nherm_basic_setup` (f11brc)).
Constraint: **lwork** \geq 120.
Note: although the minimum value of **lwork** ensures the correct functioning of `nag_sparse_nherm_basic_diagnostic` (f11btc), a larger value is required by the iterative solver `nag_sparse_nherm_basic_solver` (f11bsc) (see also `nag_sparse_nherm_basic_setup` (f11brc)).
- 8: **fail** – NagError * *Input/Output*
The NAG error argument (see Section 3.6 in the Essential Introduction).

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.
See Section 3.2.1.2 in the Essential Introduction for further information.

NE_BAD_PARAM

On entry, argument $\langle value \rangle$ had an illegal value.

NE_INT

On entry, **lwork** = $\langle value \rangle$.
Constraint: **lwork** \geq 120.

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please contact NAG for assistance.

An unexpected error has been triggered by this function. Please contact NAG.
See Section 3.6.6 in the Essential Introduction for further information.

NE_NO_LICENCE

Your licence key may have expired or may not have been installed correctly.
See Section 3.6.5 in the Essential Introduction for further information.

NE_OUT_OF_SEQUENCE

nag_sparse_nherm_basic_diagnostic (f11btc) has been called out of sequence.

7 Accuracy

Not applicable.

8 Parallelism and Performance

Not applicable.

9 Further Comments

None.

10 Example

See Section 10 in nag_sparse_nherm_basic_setup (f11brc).
