

NAG Library Function Document

nag_dsp_norm (f16rdc)

1 Purpose

nag_dsp_norm (f16rdc) calculates the value of the 1-norm, the ∞ -norm, the Frobenius norm or the maximum absolute value of the elements of a real n by n symmetric matrix, stored in packed form.

2 Specification

```
#include <nag.h>
#include <nagf16.h>
void nag_dsp_norm (Nag_OrderType order, Nag_NormType norm,
                    Nag_UptoType uplo, Integer n, const double ap[], double *r,
                    NagError *fail)
```

3 Description

Given a real n by n symmetric matrix, A , in packed storage, nag_dsp_norm (f16rdc) calculates one of the values given by

$$\|A\|_1 = \max_j \sum_{i=1}^n |a_{ij}|,$$

$$\|A\|_\infty = \max_i \sum_{j=1}^n |a_{ij}|,$$

$$\|A\|_F = \left(\sum_{i=1}^n \sum_{j=1}^n |a_{ij}|^2 \right)^{1/2}$$

or

$$\max_{i,j} |a_{ij}|.$$

Note that, since A is symmetric, $\|A\|_1 = \|A\|_\infty$.

4 References

Basic Linear Algebra Subprograms Technical (BLAST) Forum (2001) *Basic Linear Algebra Subprograms Technical (BLAST) Forum Standard* University of Tennessee, Knoxville, Tennessee <http://www.netlib.org/blas/blast-forum/blas-report.pdf>

5 Arguments

1: **order** – Nag_OrderType *Input*

On entry: the **order** argument specifies the two-dimensional storage scheme being used, i.e., row-major ordering or column-major ordering. C language defined storage is specified by **order** = Nag_RowMajor. See Section 3.2.1.3 in the Essential Introduction for a more detailed explanation of the use of this argument.

Constraint: **order** = Nag_RowMajor or Nag_ColMajor.

2:	norm – Nag_NormType	<i>Input</i>
<i>On entry:</i> specifies the value to be returned.		
	norm = Nag_OneNorm	
	The 1-norm.	
	norm = Nag_InfNorm	
	The ∞ -norm.	
	norm = Nag_FrobeniusNorm	
	The Frobenius (or Euclidean) norm.	
	norm = Nag_MaxNorm	
	The value $\max_{i,j} a_{ij} $ (not a norm).	
<i>Constraint:</i> norm = Nag_OneNorm, Nag_InfNorm, Nag_FrobeniusNorm or Nag_MaxNorm.		
3:	uplo – Nag_UptoType	<i>Input</i>
<i>On entry:</i> specifies whether the upper or lower triangular part of A is stored.		
	uplo = Nag_Upper	
	The upper triangular part of A is stored.	
	uplo = Nag_Lower	
	The lower triangular part of A is stored.	
<i>Constraint:</i> uplo = Nag_Upper or Nag_Lower.		
4:	n – Integer	<i>Input</i>
<i>On entry:</i> n , the order of the matrix A .		
If $n = 0$, then n is set to zero.		
<i>Constraint:</i> n ≥ 0 .		
5:	ap [<i>dim</i>] – const double	<i>Input</i>
Note: the dimension, <i>dim</i> , of the array ap must be at least $\max(1, \mathbf{n} \times (\mathbf{n} + 1)/2)$.		
<i>On entry:</i> the n by n symmetric matrix A , packed by rows or columns.		
The storage of elements A_{ij} depends on the order and uplo arguments as follows:		
if order = 'Nag_ColMajor' and uplo = 'Nag_Upper', A_{ij} is stored in ap [($j - 1$) \times $j/2 + i - 1$], for $i \leq j$;		
if order = 'Nag_ColMajor' and uplo = 'Nag_Lower', A_{ij} is stored in ap [($2n - j$) \times ($j - 1$) $/2 + i - 1$], for $i \geq j$;		
if order = 'Nag_RowMajor' and uplo = 'Nag_Upper', A_{ij} is stored in ap [($2n - i$) \times ($i - 1$) $/2 + j - 1$], for $i \leq j$;		
if order = 'Nag_RowMajor' and uplo = 'Nag_Lower', A_{ij} is stored in ap [($i - 1$) \times $i/2 + j - 1$], for $i \geq j$.		
6:	r – double *	<i>Output</i>
<i>On exit:</i> the value of the norm specified by norm .		
7:	fail – NagError *	<i>Input/Output</i>
The NAG error argument (see Section 3.6 in the Essential Introduction).		

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.

NE_BAD_PARAM

On entry, argument $\langle value \rangle$ had an illegal value.

NE_INT

On entry, $\mathbf{n} = \langle value \rangle$.

Constraint: $\mathbf{n} \geq 0$.

7 Accuracy

The BLAS standard requires accurate implementations which avoid unnecessary over/underflow (see Section 2.7 of Basic Linear Algebra Subprograms Technical (BLAST) Forum (2001)).

8 Parallelism and Performance

Not applicable.

9 Further Comments

None.

10 Example

See Section 10 in nag_dppcon (f07ggc) and nag_dspcon (f07pgc).
