

NAG Library Function Document

nag_bessel_j0_vector (s17asc)

1 Purpose

nag_bessel_j0_vector (s17asc) returns an array of values of the Bessel function $J_0(x)$.

2 Specification

```
#include <nag.h>
#include <nags.h>
void nag_bessel_j0_vector (Integer n, const double x[], double f[],
                           Integer invalid[], NagError *fail)
```

3 Description

nag_bessel_j0_vector (s17asc) evaluates an approximation to the Bessel function of the first kind $J_0(x_i)$ for an array of arguments x_i , for $i = 1, 2, \dots, n$.

Note: $J_0(-x) = J_0(x)$, so the approximation need only consider $x \geq 0$.

The function is based on three Chebyshev expansions:

For $0 < x \leq 8$,

$$J_0(x) = \sum_{r=0} a_r T_r(t), \quad \text{with } t = 2\left(\frac{x}{8}\right)^2 - 1.$$

For $x > 8$,

$$J_0(x) = \sqrt{\frac{2}{\pi x}} \left\{ P_0(x) \cos\left(x - \frac{\pi}{4}\right) - Q_0(x) \sin\left(x - \frac{\pi}{4}\right) \right\},$$

where $P_0(x) = \sum_{r=0} b_r T_r(t)$,

and $Q_0(x) = \frac{8}{x} \sum_{r=0} c_r T_r(t)$,

with $t = 2\left(\frac{8}{x}\right)^2 - 1$.

For x near zero, $J_0(x) \simeq 1$. This approximation is used when x is sufficiently small for the result to be correct to **machine precision**.

For very large x , it becomes impossible to provide results with any reasonable accuracy (see Section 7), hence the function fails. Such arguments contain insufficient information to determine the phase of oscillation of $J_0(x)$; only the amplitude, $\sqrt{\frac{2}{\pi|x|}}$, can be determined and this is returned on failure. The range for which this occurs is roughly related to **machine precision**; the function will fail if $|x| \gtrsim 1/\text{machine precision}$ (see the Users' Note for your implementation for details).

4 References

Abramowitz M and Stegun I A (1972) *Handbook of Mathematical Functions* (3rd Edition) Dover Publications

Clenshaw C W (1962) Chebyshev Series for Mathematical Functions *Mathematical tables* HMSO

5 Arguments

1:	n – Integer	<i>Input</i>
	<i>On entry:</i> n , the number of points.	
	<i>Constraint:</i> $\mathbf{n} \geq 0$.	
2:	x[n] – const double	<i>Input</i>
	<i>On entry:</i> the argument x_i of the function, for $i = 1, 2, \dots, n$.	
3:	f[n] – double	<i>Output</i>
	<i>On exit:</i> $J_0(x_i)$, the function values.	
4:	invalid[n] – Integer	<i>Output</i>
	<i>On exit:</i> $\mathbf{invalid}[i - 1]$ contains the error code for x_i , for $i = 1, 2, \dots, n$.	
	invalid[i - 1] = 0	
	No error.	
	invalid[i - 1] = 1	
	On entry, x_i is too large. $\mathbf{f}[i - 1]$ contains the amplitude of the J_0 oscillation, $\sqrt{\frac{2}{\pi x_i }}$.	
5:	fail – NagError *	<i>Input/Output</i>
	The NAG error argument (see Section 3.6 in the Essential Introduction).	

6 Error Indicators and Warnings

NE_BAD_PARAM

On entry, argument $\langle value \rangle$ had an illegal value.

NE_INT

On entry, $\mathbf{n} = \langle value \rangle$.
Constraint: $\mathbf{n} \geq 0$.

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please contact NAG for assistance.

NW_INVALID

On entry, at least one value of **x** was invalid.
Check **invalid** for more information.

7 Accuracy

Let δ be the relative error in the argument and E be the absolute error in the result. (Since $J_0(x)$ oscillates about zero, absolute error and not relative error is significant.)

If δ is somewhat larger than the **machine precision** (e.g., if δ is due to data errors etc.), then E and δ are approximately related by:

$$E \simeq |xJ_1(x)|\delta$$

(provided E is also within machine bounds). Figure 1 displays the behaviour of the amplification factor $|xJ_1(x)|$.

However, if δ is of the same order as ***machine precision***, then rounding errors could make E slightly larger than the above relation predicts.

For very large x , the above relation ceases to apply. In this region, $J_0(x) \simeq \sqrt{\frac{2}{\pi|x|}} \cos\left(x - \frac{\pi}{4}\right)$. The amplitude $\sqrt{\frac{2}{\pi|x|}}$ can be calculated with reasonable accuracy for all x , but $\cos\left(x - \frac{\pi}{4}\right)$ cannot. If $x - \frac{\pi}{4}$ is written as $2N\pi + \theta$ where N is an integer and $0 \leq \theta < 2\pi$, then $\cos\left(x - \frac{\pi}{4}\right)$ is determined by θ only. If $x \gtrsim \delta^{-1}$, θ cannot be determined with any accuracy at all. Thus if x is greater than, or of the order of, the inverse of the ***machine precision***, it is impossible to calculate the phase of $J_0(x)$ and the function must fail.




Figure 1

8 Parallelism and Performance

Not applicable.

9 Further Comments

None.

10 Example

This example reads values of x from a file, evaluates the function at each value of x_i and prints the results.

10.1 Program Text

```
/* nag_bessel_j0_vector (s17asc) Example Program.
*
* Copyright 2011, Numerical Algorithms Group.
*
* Mark 23 2011.
*/
#include <nag.h>
#include <stdio.h>
```

```

#include <nag_stdlib.h>
#include <nags.h>

int main(void)
{
    Integer exit_status = 0;
    Integer i, n;
    double *f = 0, *x = 0;
    Integer *invalid = 0;
    NagError fail;

    INIT_FAIL(fail);

    /* Skip heading in data file */
    scanf("%*[^\n]");

    printf("nag_bessel_j0_vector (s17asc) Example Program Results\n");
    printf("\n");
    printf("      x          f          invalid\n");
    printf("\n");
    scanf("%ld", &n);
    scanf("%*[^\n]");

    /* Allocate memory */
    if (!(x = NAG_ALLOC(n, double)) ||
        !(f = NAG_ALLOC(n, double)) ||
        !(invalid = NAG_ALLOC(n, Integer)))
    {
        printf("Allocation failure\n");
        exit_status = -1;
        goto END;
    }

    for (i=0; i<n; i++)
        scanf("%lf", &x[i]);
    scanf("%*[^\n]");

    /* nag_bessel_j0_vector (s17asc).
     * Bessel function J_0(x)
     */
    nag_bessel_j0_vector(n, x, f, invalid, &fail);
    if (fail.code!=NE_NOERROR && fail.code!=NW_INVALID)
    {
        printf("Error from nag_bessel_j0_vector (s17asc).\n%s\n",
               fail.message);
        exit_status = 1;
        goto END;
    }

    for (i=0; i<n; i++)
        printf(" %11.3e %11.3e %4ld\n", x[i], f[i], invalid[i]);

END:
    NAG_FREE(f);
    NAG_FREE(x);
    NAG_FREE(invalid);

    return exit_status;
}

```

10.2 Program Data

nag_bessel_j0_vector (s17asc) Example Program Data

9

0.0 0.5 1.0 3.0 6.0 8.0 10.0 -1.0 1000.0

10.3 Program Results

nag_bessel_j0_vector (s17asc) Example Program Results

x	f	iinvalid
0.000e+00	1.000e+00	0
5.000e-01	9.385e-01	0
1.000e+00	7.652e-01	0
3.000e+00	-2.601e-01	0
6.000e+00	1.506e-01	0
8.000e+00	1.717e-01	0
1.000e+01	-2.459e-01	0
-1.000e+00	7.652e-01	0
1.000e+03	2.479e-02	0