

# NAG Library Function Document

## nag\_zhb\_norm (f16uec)

### 1 Purpose

nag\_zhb\_norm (f16uec) calculates the value of the 1-norm, the  $\infty$ -norm, the Frobenius norm or the maximum absolute value of the elements of a complex  $n$  by  $n$  Hermitian band matrix.

### 2 Specification

```
#include <nag.h>
#include <nagf16.h>

void nag_zhb_norm (Nag_OrderType order, Nag_NormType norm,
                  Nag_UploType uplo, Integer n, Integer k, const Complex ab[],
                  Integer pdab, double *r, NagError *fail)
```

### 3 Description

Given a complex  $n$  by  $n$  Hermitian band matrix,  $A$ , nag\_zhb\_norm (f16uec) calculates one of the values given by

$$\|A\|_1 = \max_j \sum_{i=1}^n |a_{ij}|,$$

$$\|A\|_\infty = \max_i \sum_{j=1}^n |a_{ij}|,$$

$$\|A\|_F = \left( \sum_{i=1}^n \sum_{j=1}^n |a_{ij}|^2 \right)^{1/2}$$

or

$$\max_{i,j} |a_{ij}|.$$

Note that, since  $A$  is symmetric,  $\|A\|_1 = \|A\|_\infty$ .

### 4 References

Basic Linear Algebra Subprograms Technical (BLAST) Forum (2001) *Basic Linear Algebra Subprograms Technical (BLAST) Forum Standard* University of Tennessee, Knoxville, Tennessee <http://www.netlib.org/blas/blast-forum/blas-report.pdf>

### 5 Arguments

1: **order** – Nag\_OrderType *Input*

*On entry:* the **order** argument specifies the two-dimensional storage scheme being used, i.e., row-major ordering or column-major ordering. C language defined storage is specified by **order** = Nag\_RowMajor. See Section 2.3.1.3 in How to Use the NAG Library and its Documentation for a more detailed explanation of the use of this argument.

*Constraint:* **order** = Nag\_RowMajor or Nag\_ColMajor.

2: **norm** – Nag\_NormType Input

*On entry:* specifies the value to be returned.

**norm** = Nag\_OneNorm  
The 1-norm.

**norm** = Nag\_InfNorm  
The  $\infty$ -norm.

**norm** = Nag\_FrobeniusNorm  
The Frobenius (or Euclidean) norm.

**norm** = Nag\_MaxNorm  
The value  $\max_{i,j} |a_{ij}|$  (not a norm).

*Constraint:* **norm** = Nag\_OneNorm, Nag\_InfNorm, Nag\_FrobeniusNorm or Nag\_MaxNorm.

3: **uplo** – Nag\_UploType Input

*On entry:* specifies whether the upper or lower triangular part of  $A$  is stored.

**uplo** = Nag\_Upper  
The upper triangular part of  $A$  is stored.

**uplo** = Nag\_Lower  
The lower triangular part of  $A$  is stored.

*Constraint:* **uplo** = Nag\_Upper or Nag\_Lower.

4: **n** – Integer Input

*On entry:*  $n$ , the order of the matrix  $A$ .

If  $n = 0$ , then **n** is set to zero.

*Constraint:* **n**  $\geq 0$ .

5: **k** – Integer Input

*On entry:*  $k$ , the number of subdiagonals or superdiagonals of the matrix  $A$ .

*Constraint:* **k**  $\geq 0$ .

6: **ab**[*dim*] – const Complex Input

**Note:** the dimension, *dim*, of the array **ab** must be at least  $\max(1, \mathbf{pdab} \times \mathbf{n})$ .

*On entry:* the  $n$  by  $n$  Hermitian band matrix  $A$ .

This is stored as a notional two-dimensional array with row elements or column elements stored contiguously. The storage of elements of  $A_{ij}$ , depends on the **order** and **uplo** arguments as follows:

if **order** = Nag\_ColMajor and **uplo** = Nag\_Upper,  
 $A_{ij}$  is stored in **ab**[ $k + i - j + (j - 1) \times \mathbf{pdab}$ ], for  $j = 1, \dots, n$  and  
 $i = \max(1, j - k), \dots, j$ ;  
 if **order** = Nag\_ColMajor and **uplo** = Nag\_Lower,  
 $A_{ij}$  is stored in **ab**[ $i - j + (j - 1) \times \mathbf{pdab}$ ], for  $j = 1, \dots, n$  and  
 $i = j, \dots, \min(n, j + k)$ ;  
 if **order** = Nag\_RowMajor and **uplo** = Nag\_Upper,  
 $A_{ij}$  is stored in **ab**[ $j - i + (i - 1) \times \mathbf{pdab}$ ], for  $i = 1, \dots, n$  and  
 $j = i, \dots, \min(n, i + k)$ ;  
 if **order** = Nag\_RowMajor and **uplo** = Nag\_Lower,  
 $A_{ij}$  is stored in **ab**[ $k + j - i + (i - 1) \times \mathbf{pdab}$ ], for  $i = 1, \dots, n$  and  
 $j = \max(1, i - k), \dots, i$ .

- 7: **pdab** – Integer *Input*  
*On entry:* the stride separating row or column elements (depending on the value of **order**) of the matrix *A* in the array **ab**.  
*Constraint:* **pdab**  $\geq$  **k** + 1.
- 8: **r** – double \* *Output*  
*On exit:* the value of the norm specified by **norm**.
- 9: **fail** – NagError \* *Input/Output*  
The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).

## 6 Error Indicators and Warnings

### NE\_ALLOC\_FAIL

Dynamic memory allocation failed.  
See Section 3.2.1.2 in How to Use the NAG Library and its Documentation for further information.

### NE\_BAD\_PARAM

On entry, argument *<value>* had an illegal value.

### NE\_INT

On entry, **k** = *<value>*.

Constraint: **k**  $\geq$  0.

On entry, **n** = *<value>*.

Constraint: **n**  $\geq$  0.

### NE\_INT\_2

On entry, **pdab** = *<value>*, **k** = *<value>*.

Constraint: **pdab**  $\geq$  **k** + 1.

### NE\_INTERNAL\_ERROR

An unexpected error has been triggered by this function. Please contact NAG.  
See Section 3.6.6 in How to Use the NAG Library and its Documentation for further information.

### NE\_NO\_LICENCE

Your licence key may have expired or may not have been installed correctly.  
See Section 3.6.5 in How to Use the NAG Library and its Documentation for further information.

## 7 Accuracy

The BLAS standard requires accurate implementations which avoid unnecessary over/underflow (see Section 2.7 of Basic Linear Algebra Subprograms Technical (BLAST) Forum (2001)).

## 8 Parallelism and Performance

nag\_zhb\_norm (f16uec) is not threaded in any implementation.

## **9 Further Comments**

None.

## **10 Example**

See Section 10 in nag\_zpbcon (f07huc).

---