

NAG Library Function Document

nag_ip_read (h02xyc)

1 Purpose

nag_ip_read (h02xyc) reads a set of optional parameter values from a file and assigns those values to a given options structure of type Nag_H02_Opt. Values supplied are checked as being of correct type and within range for the specified optional parameter.

2 Specification

```
#include <nag.h>
#include <nagh.h>
void nag_ip_read (const char *name, const char *opt_file,
                  Nag_H02_Opt *options, Nag_Boolean print, const char *outfile,
                  NagError *fail)
```

3 Description

The integer programming (IP) functions of the h Chapter Introduction have a number of optional parameters, which are set by means of a structure of type Nag_H02_Opt. Optional parameter values may be assigned to members of the options structure directly in the program text and/or by supplying the optional values in a file which can be read by the function nag_ip_read (h02xyc).

When optional parameter values are read from a file using nag_ip_read (h02xyc) then the options structure will be initialized automatically if this has not already been done. It is only necessary to call nag_ip_init (h02xxc) if direct assignments to the options structure are made in your program before calling nag_ip_read (h02xyc).

As well as reading from a file, nag_ip_read (h02xyc) will also read from `stdin`. This allows redirection to be used to supply the file; it also permits nag_ip_read (h02xyc) to be used interactively with you supplying values from the keyboard.

Checks are made that the values read in are of valid type for the optional parameter specified and that the value is within the valid range for that argument. If a value is accepted, a printed confirmation of the setting of the relevant argument will be output if `print` = Nag_TRUE. An unacceptable argument name or value will give an error message if `print` = Nag_FALSE.

4 References

None.

5 Arguments

1: **name** – const char * *Input*

On entry: a character string specifying either the NAG six character name or the NAG long name of the proposed IP function. The case of the character string is disregarded.

2: **opt_file** – const char * *Input*

On entry: the name of the file which specifies the optional parameter values. If `stdin` is to be used, the string "stdin" should be supplied. The set of option values must be preceded by the keyword begin followed by the function name for which the set of options is being supplied. The function name may be the six character NAG name of an IP function or its associated long name.

Each option value specified in the file must be preceded by the name of the optional parameter. The argument name and value must be separated by at least one blank space or an equals symbol. nag_ip_read (h02xyc) will read to the end of file or until the keyword `end` is found or until another `begin` is found. C style comments may be placed within a set of option values to aid your documentation. Outside the option value sets, text need not be within C style comment delimiters.

N.B. Assignment to function pointers in the options structure, memory allocation to array pointers and assignment of trailing array dimensions cannot be performed from an options file. These must be assigned directly to the options structure in your calling program.

3: **options** – Nag_H02_Opt * *Input/Output*

On entry: the options structure may or may not have previously been initialized, and had values assigned to its members.

On exit: the options structure, initialized and with values assigned according to the values found in the options file.

4: **print** – Nag_Boolean *Input*

On entry: if Nag_TRUE a message confirming the setting of each option will be output.

5: **outfile** – const char * *Input*

On entry: a character string specifying the name of the file to which confirmation messages should be output. If `stdout` is required then the string "stdout" should be given. When **print** = Nag_FALSE the empty string "" can be supplied as **outfile** will be ignored.

6: **fail** – NagError * *Input/Output*

The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).

6 Error Indicators and Warnings

NE_FIELD_UNKNOWN

(line $\langle value \rangle$) ' $\langle string \rangle$ ' is not a permitted structure member or option for $\langle string \rangle$.

NE_INVALID_BEGIN

The Begin statement occurring in data file from which options are being read is not valid.

NE_INVALID_ENUM_RANGE

Enum value $\langle string \rangle$ given to $\langle option \rangle$ is not valid for this function.

NE_INVALID_INT_RANGE_1

NE_INVALID_OPTION

(line $\langle value \rangle$) ' $\langle string \rangle$ ' cannot be assigned to using an options file.

NE_INVALID_OPTION_NAME

(line $\langle value \rangle$) ' $\langle string \rangle$ ' is not a valid name for a structure member or option.

This error message is output if, for example, the specified string contains characters which are not permitted in a variable name in the C programming language.

NE_INVALID_REAL_RANGE_CONS

Value $\langle value \rangle$ given to $\langle option \rangle$ is not valid. The argument $\langle option \rangle$ must satisfy $\langle constraint \rangle$.

NE_INVALID_REAL_RANGE_F

Value $\langle value \rangle$ given to $\langle option \rangle$ is not valid. Correct range is $\langle option \rangle \langle value \rangle$.

NE_INVALID_REAL_RANGE_FF

Value $\langle value \rangle$ given to $\langle option \rangle$ is not valid. Correct range is $\langle value \rangle \langle option \rangle \langle value \rangle$.

NE_INVALID_TEXT_RANGE

Value $\langle string \rangle$ given to $\langle option \rangle$ not valid.

NE_INVALID_VALUE

(line $\langle value \rangle$) value ‘ $\langle string \rangle$ ’ given to $\langle string \rangle$ option is not of the correct type for this option.

NE_NO_VALUE

(line $\langle value \rangle$) no value found for option $\langle string \rangle$.

NE_NOT_APPEND_FILE

Cannot open file $\langle string \rangle$ for appending.

NE_NOT_CLOSE_FILE

Cannot close file $\langle string \rangle$.

NE_NOT_FUN_NAME

The string, $\langle string \rangle$, supplied in the argument name is not the name of any C Library function with option setting facilities.

NE_NOT_READ_FILE

Cannot open file $\langle string \rangle$ for reading.

NE_UNBALANCED_COMMENT

Unbalanced comment starting on line $\langle value \rangle$ found in options file.

NE_WRITE_ERROR

Error occurred when writing to file $\langle string \rangle$.

7 Accuracy

Not applicable.

8 Parallelism and Performance

nag_ip_read (h02xyc) is not threaded in any implementation.

9 Further Comments

nag_ip_read (h02xyc) may be used to read the optional ‘MPSX names’ (e.g., **prob.name**, **obj.name**) for nag_ip_mps_read (h02buc). However, although this function allows the names to contain non-leading blank characters, nag_ip_read (h02xyc) will not read such names correctly from an options file since blank spaces are assumed to denote the end of an option name or value within the file. All other

valid MPSX names (see the documentation for nag_ip_mps_read (h02buc) for details) will be read correctly by nag_ip_read (h02xyc).

10 Example

See Section 10 in nag_ip_mps_read (h02buc).
