

NAG Library Routine Document

G05SHF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

G05SHF generates a vector of pseudorandom numbers taken from an F (or Fisher's variance ratio) distribution with μ and ν degrees of freedom.

2 Specification

```
SUBROUTINE G05SHF (N, DF1, DF2, STATE, X, IFAIL)
  INTEGER          N, DF1, DF2, STATE(*), IFAIL
  REAL (KIND=nag_wp) X(N)
```

3 Description

The distribution has PDF (probability density function)

$$f(x) = \frac{\left(\frac{\mu+\nu-2}{2}\right)! x^{\frac{1}{2}(\mu-1)}}{\left(\frac{1}{2}\mu-1\right)! \left(\frac{1}{2}\nu-1\right)! \left(1 + \frac{\mu}{\nu}x\right)^{\frac{1}{2}(\mu+\nu)}} \times \left(\frac{\mu}{\nu}\right)^{\frac{1}{2}\mu} \quad \text{if } x > 0,$$

$$f(x) = 0 \quad \text{otherwise.}$$

G05SHF calculates the values

$$\frac{\nu y_i}{\mu z_i}, \quad i = 1, 2, \dots, n,$$

where y_i and z_i are generated by G05SJF from gamma distributions with parameters $\left(\frac{1}{2}\mu, 2\right)$ and $\left(\frac{1}{2}\nu, 2\right)$ respectively (i.e., from χ^2 -distributions with μ and ν degrees of freedom).

One of the initialization routines G05KFF (for a repeatable sequence if computed sequentially) or G05KGF (for a non-repeatable sequence) must be called prior to the first call to G05SHF.

4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison–Wesley

5 Parameters

1: N – INTEGER *Input*

On entry: n , the number of pseudorandom numbers to be generated.

Constraint: $N \geq 0$.

2: DF1 – INTEGER *Input*

On entry: μ , the number of degrees of freedom of the distribution.

Constraint: $DF1 \geq 1$.

- 3: DF2 – INTEGER *Input*
On entry: ν , the number of degrees of freedom of the distribution.
Constraint: $DF2 \geq 1$.
- 4: STATE(*) – INTEGER array *Communication Array*
Note: the actual argument supplied must be the array STATE supplied to the initialization routines G05KFF or G05KGF.
On entry: contains information on the selected base generator and its current state.
On exit: contains updated information on the state of the generator.
- 5: X(N) – REAL (KIND=nag_wp) array *Output*
On exit: the n pseudorandom numbers from the specified F -distribution.
- 6: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**
On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1 , explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, $N < 0$.

IFAIL = 2

On entry, $DF1 < 1$.

IFAIL = 3

On entry, $DF2 < 1$.

IFAIL = 4

On entry, STATE vector was not initialized or has been corrupted.

7 Accuracy

Not applicable.

8 Further Comments

The time taken by G05SHF increases with μ and ν .

9 Example

This example prints five pseudorandom numbers from an F -distribution with two and three degrees of freedom, generated by a single call to G05SHF, after initialization by G05KFF.

9.1 Program Text

```

Program g05shfe

!      G05SHF Example Program Text

!      Mark 24 Release. NAG Copyright 2012.

!      .. Use Statements ..
      Use nag_library, Only: g05kff, g05shf, nag_wp
!      .. Implicit None Statement ..
      Implicit None
!      .. Parameters ..
      Integer, Parameter          :: lseed = 1, nin = 5, nout = 6
!      .. Local Scalars ..
      Integer                    :: df1, df2, genid, ifail, lstate, n,    &
                                subid
!      .. Local Arrays ..
      Real (Kind=nag_wp), Allocatable :: x(:)
      Integer                        :: seed(lseed)
      Integer, Allocatable           :: state(:)
!      .. Executable Statements ..
      Write (nout,*) 'G05SHF Example Program Results'
      Write (nout,*)

!      Skip heading in data file
      Read (nin,*)

!      Read in the base generator information and seed
      Read (nin,*) genid, subid, seed(1)

!      Initial call to initialiser to get size of STATE array
      lstate = 0
      Allocate (state(lstate))
      ifail = 0
      Call g05kff(genid,subid,seed,lseed,state,lstate,ifail)

!      Reallocate STATE
      Deallocate (state)
      Allocate (state(lstate))

!      Initialize the generator to a repeatable sequence
      ifail = 0
      Call g05kff(genid,subid,seed,lseed,state,lstate,ifail)

!      Read in sample size
      Read (nin,*) n

      Allocate (x(n))

!      Read in the distribution parameters
      Read (nin,*) df1, df2

!      Generate the variates
      ifail = 0
      Call g05shf(n,df1,df2,state,x,ifail)

!      Display the variates
      Write (nout,99999) x(1:n)

99999 Format (1X,F10.4)
      End Program g05shfe

```

9.2 Program Data

```
G05SHF Example Program Data
1 1 1762543      :: GENID,SUBID,SEED(1)
5 3              :: N,NMIX
2 3              :: DF1,DF2
```

9.3 Program Results

G05SHF Example Program Results

```
1.4401
1.8083
0.3638
0.5464
4.0895
```
