

NAG Toolbox

nag_specfun_bessel_j1_real (s17af)

1 Purpose

nag_specfun_bessel_j1_real (s17af) returns the value of the Bessel function $J_1(x)$, via the function name.

2 Syntax

```
[result, ifail] = nag_specfun_bessel_j1_real(x)
[result, ifail] = s17af(x)
```

3 Description

nag_specfun_bessel_j1_real (s17af) evaluates an approximation to the Bessel function of the first kind $J_1(x)$.

Note: $J_1(-x) = -J_1(x)$, so the approximation need only consider $x \geq 0$.

The function is based on three Chebyshev expansions:

For $0 < x \leq 8$,

$$J_1(x) = \frac{x}{8} \sum_{r=0} a_r T_r(t), \quad \text{with } t = 2\left(\frac{x}{8}\right)^2 - 1.$$

For $x > 8$,

$$J_1(x) = \sqrt{\frac{2}{\pi x}} \left\{ P_1(x) \cos\left(x - \frac{3\pi}{4}\right) - Q_1(x) \sin\left(x - \frac{3\pi}{4}\right) \right\}$$

where $P_1(x) = \sum_{r=0} b_r T_r(t)$,

and $Q_1(x) = \frac{8}{x} \sum_{r=0} c_r T_r(t)$,

with $t = 2\left(\frac{8}{x}\right)^2 - 1$.

For x near zero, $J_1(x) \simeq \frac{x}{2}$. This approximation is used when x is sufficiently small for the result to be correct to **machine precision**.

For very large x , it becomes impossible to provide results with any reasonable accuracy (see Section 7), hence the function fails. Such arguments contain insufficient information to determine the phase of oscillation of $J_1(x)$; only the amplitude, $\sqrt{\frac{2}{\pi|x|}}$, can be determined and this is returned on softfailure.

The range for which this occurs is roughly related to **machine precision**; the function will fail if $|x| \gtrsim 1/\text{machine precision}$.

4 References

Abramowitz M and Stegun I A (1972) *Handbook of Mathematical Functions* (3rd Edition) Dover Publications

Clenshaw C W (1962) Chebyshev Series for Mathematical Functions *Mathematical tables* HMSO

5 Parameters

5.1 Compulsory Input Parameters

- 1: **x** – REAL (KIND=nag_wp)
The argument x of the function.

5.2 Optional Input Parameters

None.

5.3 Output Parameters

- 1: **result**
The result of the function.
- 2: **ifail** – INTEGER
ifail = 0 unless the function detects an error (see Section 5).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

ifail = 1

x is too large. On softfailure the function returns the amplitude of the J_1 oscillation, $\sqrt{\frac{2}{\pi|x|}}$.

ifail = -99

An unexpected error has been triggered by this routine. Please contact NAG.

ifail = -399

Your licence key may have expired or may not have been installed correctly.

ifail = -999

Dynamic memory allocation failed.

7 Accuracy

Let δ be the relative error in the argument and E be the absolute error in the result. (Since $J_1(x)$ oscillates about zero, absolute error and not relative error is significant.)

If δ is somewhat larger than *machine precision* (e.g., if δ is due to data errors etc.), then E and δ are approximately related by:

$$E \simeq |xJ_0(x) - J_1(x)|\delta$$

(provided E is also within machine bounds). Figure 1 displays the behaviour of the amplification factor $|xJ_0(x) - J_1(x)|$.

However, if δ is of the same order as *machine precision*, then rounding errors could make E slightly larger than the above relation predicts.

For very large x , the above relation ceases to apply. In this region, $J_1(x) \simeq \sqrt{\frac{2}{\pi|x|}} \cos\left(x - \frac{3\pi}{4}\right)$. The amplitude $\sqrt{\frac{2}{\pi|x|}}$ can be calculated with reasonable accuracy for all x , but $\cos\left(x - \frac{3\pi}{4}\right)$ cannot. If

$x - \frac{3\pi}{4}$ is written as $2N\pi + \theta$ where N is an integer and $0 \leq \theta < 2\pi$, then $\cos\left(x - \frac{3\pi}{4}\right)$ is determined by θ only. If $x \gtrsim \delta^{-1}$, θ cannot be determined with any accuracy at all. Thus if x is greater than, or of the order of, the reciprocal of *machine precision*, it is impossible to calculate the phase of $J_1(x)$ and the function must fail.




Figure 1

8 Further Comments

None.

9 Example

This example reads values of the argument x from a file, evaluates the function at each value of x and prints the results.

9.1 Program Text

```
function s17af_example

fprintf('s17af example results\n\n');

x = [0    0.5    1    3    6    8    10   -1  1000];
n = size(x,2);
result = x;

for j=1:n
    [result(j), ifail] = s17af(x(j));
end

disp('      x      J_1(x)');
fprintf('%12.3e%12.3e\n',[x; result]);

s17af_plot;

function s17af_plot
x = [-30:0.25:30];
for j = 1:numel(x)
    [J1(j), ifail] = s17af(x(j));
```

```
end

fig1 = figure;
plot(x,J1,'-r');
xlabel('x');
ylabel('J_1(x)');
title('Bessel Function J_1(x)');
axis([-30 30 -0.6 0.6]);

% print(fig1,'-dpng','-r75','s17af_fig1.png');
% print(fig1,'-deps','-r75','s17af_fig1.eps');
```

9.2 Program Results

s17af example results

x	J ₁ (x)
0.000e+00	0.000e+00
5.000e-01	2.423e-01
1.000e+00	4.401e-01
3.000e+00	3.391e-01
6.000e+00	-2.767e-01
8.000e+00	2.346e-01
1.000e+01	4.347e-02
-1.000e+00	-4.401e-01
1.000e+03	4.728e-03

