

NAG Library Routine Document

F06PAF (DGEMV)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F06PAF (DGEMV) computes the matrix-vector product for a real general matrix or its transpose.

2 Specification

```
SUBROUTINE F06PAF (TRANS, M, N, ALPHA, A, LDA, X, INCX, BETA, Y, INCY)
INTEGER          M, N, LDA, INCX, INCY
REAL (KIND=nag_wp) ALPHA, A(LDA,*), X(*), BETA, Y(*)
CHARACTER(1)    TRANS
```

The routine may be called by its BLAS name *dgemv*.

3 Description

F06PAF (DGEMV) performs one of the matrix-vector operations

$$y \leftarrow \alpha Ax + \beta y, \quad \text{or} \quad y \leftarrow \alpha A^T x + \beta y,$$

where A is an m by n real matrix, x and y are real vectors, and α and β are real scalars.

If $m = 0$ or $n = 0$, no operation is performed.

4 References

None.

5 Parameters

- | | | |
|----|--|--------------|
| 1: | TRANS – CHARACTER(1)
<i>On entry:</i> specifies the operation to be performed.
TRANS = 'N'
$y \leftarrow \alpha Ax + \beta y$.
TRANS = 'T' or 'C'
$y \leftarrow \alpha A^T x + \beta y$.
<i>Constraint:</i> TRANS = 'N', 'T' or 'C'. | <i>Input</i> |
| 2: | M – INTEGER
<i>On entry:</i> m , the number of rows of the matrix A .
<i>Constraint:</i> $M \geq 0$. | <i>Input</i> |
| 3: | N – INTEGER
<i>On entry:</i> n , the number of columns of the matrix A .
<i>Constraint:</i> $N \geq 0$. | <i>Input</i> |

- 4: ALPHA – REAL (KIND=nag_wp) Input
On entry: the scalar α .
- 5: A(LDA,*) – REAL (KIND=nag_wp) array Input
Note: the second dimension of the array A must be at least N.
On entry: the m by n matrix A .
- 6: LDA – INTEGER Input
On entry: the first dimension of the array A as declared in the (sub)program from which F06PAF (DGEMV) is called.
Constraint: $LDA \geq \max(1, M)$.
- 7: X(*) – REAL (KIND=nag_wp) array Input
Note: the dimension of the array X must be at least $\max(1, 1 + (N - 1) \times |INCX|)$ if TRANS = 'N' and at least $\max(1, 1 + (M - 1) \times |INCX|)$ if TRANS = 'T' or 'C'.
On entry: the vector x .
 If TRANS = 'N',
 if $INCX > 0$, x_i must be stored in $X(1 + (i - 1) \times INCX)$, for $i = 1, 2, \dots, N$;
 if $INCX < 0$, x_i must be stored in $X(1 - (N - i) \times INCX)$, for $i = 1, 2, \dots, N$.
 If TRANS = 'T' or 'C',
 if $INCX > 0$, x_i must be stored in $X(1 + (i - 1) \times INCX)$, for $i = 1, 2, \dots, M$;
 if $INCX < 0$, x_i must be stored in $X(1 - (M - i) \times INCX)$, for $i = 1, 2, \dots, M$.
- 8: INCX – INTEGER Input
On entry: the increment in the subscripts of X between successive elements of x .
Constraint: $INCX \neq 0$.
- 9: BETA – REAL (KIND=nag_wp) Input
On entry: the scalar β .
- 10: Y(*) – REAL (KIND=nag_wp) array Input/Output
Note: the dimension of the array Y must be at least $\max(1, 1 + (M - 1) \times |INCY|)$ if TRANS = 'N' and at least $\max(1, 1 + (N - 1) \times |INCY|)$ if TRANS = 'T' or 'C'.
On entry: the vector y , if BETA = 0.0, Y need not be set.
 If TRANS = 'N',
 if $INCY > 0$, y_i must be stored in $Y(1 + (i - 1) \times INCY)$, for $i = 1, 2, \dots, M$;
 if $INCY < 0$, y_i must be stored in $Y(1 - (M - i) \times INCY)$, for $i = 1, 2, \dots, M$.
 If TRANS = 'T' or 'C',
 if $INCY > 0$, y_i must be stored in $Y(1 + (i - 1) \times INCY)$, for $i = 1, 2, \dots, N$;
 if $INCY < 0$, y_i must be stored in $Y(1 - (N - i) \times INCY)$, for $i = 1, 2, \dots, N$.
On exit: the updated vector y stored in the array elements used to supply the original vector y .
- 11: INCY – INTEGER Input
On entry: the increment in the subscripts of Y between successive elements of y .
Constraint: $INCY \neq 0$.

6 Error Indicators and Warnings

None.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

None.
